



**X-Camera**

# X-Camera Version 2.3.1

## User's Guide

12/30/2017

Stick and Rudder Studios

## Table of Contents

Change Log.....	6
Release Notes .....	6
2.3.1 .....	6
Forced FOV on a Camera .....	6
X-Plane 11.1 and Higher.....	7
Bug Fixes .....	7
New Features .....	7
Community Airport Camera Files.....	7
Known Problems .....	8
Introduction .....	8
Licensing.....	8
Requirements.....	10
Limitations .....	10
Optional Integrations .....	11
TrackIR.....	11
SimHat.....	12
Scenic Flyer .....	12
HeadShake .....	12
XPRealistic.....	12
LinuxTrack .....	12
Recommended Hardware .....	13
Installation .....	14
Enabling X-Camera .....	15
System Check .....	15
Configuring X-Camera .....	15
Control Panel.....	16
Community Camera Files .....	18
Auto Correct.....	19
Sharing Your Camera Definition.....	20
Adding Cameras and Categories .....	21
Positioning Cameras.....	21

Keyboard Control .....	23
Mouse Move and Mouse Zoom .....	24
Field of View.....	25
Initial Zoom Factor .....	25
Panning .....	26
Mouse Look.....	26
Walk Mode.....	27
Camera Positioning with a Spare Joystick Controller .....	27
Snap to TrackIR .....	28
Camera Options .....	28
TrackIR.....	28
Limit TrackIR.....	30
HeadShake .....	31
Enable XPRealistic .....	31
Smooth Transition.....	31
Retain Mouse Look Position .....	31
Enable Temporary Positioning .....	32
View ID .....	32
Linear Transition, Bezier Transition, Auto Advance, Transition Frames, and Tracking Options.....	33
Advanced Transitions.....	33
Enable Linear Transition.....	33
Enable Bezier Transition .....	33
Transition Frame Count .....	34
Transition Seconds .....	34
Enable Auto Advance to the Next Camera .....	34
Smooth Camera Joins.....	35
Tracking Cameras .....	35
Automatically Creating Orbit and Fly-By Animations .....	37
Some Notes on Advanced Animations.....	38
External Cameras .....	39
External Camera.....	40

Scenic Flyer Panels .....	40
Cineflex Camera .....	40
Free Camera .....	41
Target Following Camera .....	41
X-Plane 9 Chase Camera .....	41
AI Perspective .....	41
Airport Cameras .....	42
Overview .....	42
Airport Camera File Types and Names.....	42
Creating Airport Cameras .....	43
Generating Airport Cameras .....	44
Horizontal and Vertical Offsets .....	45
Sign Camera Culling Radius .....	45
Forward Facing Starting Position Camera.....	45
Create Airport Targets .....	45
Airport Camera Creation Notes .....	45
Joining Airports .....	46
Selecting Airport Cameras .....	46
Airport Cameras with an Unregistered Version of X-Camera .....	47
Targets and Target Following Cameras.....	47
Creating Targets .....	48
Target Following Cameras.....	48
Free Target.....	48
Target Commands.....	49
Notes on Targets and Target Following Cameras .....	50
Mini Control Panel .....	50
Joystick Button Assignments.....	52
Sharing Camera Files.....	53
Sharing Guidelines .....	53
Settings.....	54
Pan and Movement Speeds .....	54

Auto Show Mini-Control Panel .....	55
Open Mini-Control Panel on Start .....	55
Enable Transparent Mini Control Panel.....	55
Enable Solid Control Panel.....	55
Hide Favorites in Mini Control Panel .....	55
Show Target Information.....	56
Pause When Aiming Target.....	56
Lock Keyboard Control.....	56
Mouse Smoothing.....	56
Head Track Smoothing.....	56
View Axis Smoothing.....	56
Enable Force FOV .....	56
Camera Smoothing Window .....	57
Getting Support.....	57
Tutorials .....	57
New Releases and Beta Releases.....	57
Appendix .....	58
External Integrations.....	58
Head Tracking .....	58
Previous Change Logs .....	59
Prior Release Notes.....	63
2.3 .....	63
Import X-Plane Quick Look Views .....	63
Responding to Quick Look Save and Select Commands .....	63
New External Datarefs for 3 <sup>rd</sup> Party Head Tracking .....	63
Continuous Orbit.....	63
Multi-Monitor Roll Support .....	64
New Options .....	64
Bug Fixes .....	64
Yoke Visibility .....	64
XPRealistic Integration .....	65

Moving cameras with a spare joystick controller .....	65
AI perspective .....	65
AI Perspective Scale Up and Down .....	65
2.2 .....	65
Smooth Camera Joins.....	65
Airport Camera.....	66
Walk Mode HotKey .....	66
Center of Gravity Offsets .....	66
Compatibility with X-Plane Views .....	66
New Commands .....	66
Cinema Verite Support by Camera .....	67
Copy and Paste Camera and Camera Sets .....	67
FOV Transitions .....	67
Community File Support .....	67
Mini-Control Panel .....	68
2.1.1 .....	68
2.1 .....	68
External Cameras .....	69
Responding to ATC with Commands.....	69
Scenic Flyer Integration.....	69
Restoring Camera.....	69
X-Plane 9 Chase View.....	70
Airport Cameras .....	70
Roll Support.....	70
2.0 .....	70
AI Perspective .....	<b>Error! Bookmark not defined.</b>
1.1 .....	74

## Change Log

Version	Changes
2.3.1	<ul style="list-style-type: none"><li>• Fixed a number of UI anomalies when running under X-Plane 11</li><li>• Introduced an option to enable / disable the ability to force the FOV on a camera. This was causing a lot of problems with Multi-Monitor setups and caused a great deal of confusion when trying to adjust the FOV in the X-Plane graphics settings.</li><li>• X-Camera windows binaries are now being built as Release versions cutting down their size but not affecting functionality.</li><li>• Add support for the ten extra quick look commands in X-Plane 11.1</li><li>• Fixed a bug where the yoke visibility camera option was only being saved as a Boolean when it really needed to be saved as a tri-state value. Note you will need to correct any cameras and resave the camera file.</li><li>• Increased Joystick axis array size from 250 to 500 slots per the new size in X-Plane 11.10</li><li>• Added view axis calibration and adjustable view axis null zone</li><li>• Fixed a bug where the default Field of View was not getting restored if you were on a camera that forced a field of view setting and then selected an X-Plane view while leaving X-Camera enabled</li><li>• Fixed bugs in View and Camera axis inputs</li><li>• Added View and Camera axis smoothing</li><li>• Fixed bug where camera axis input was only handling the first 100 axis assignments in X-Plane 11 when it needed to be 250 in X-Plane 11</li><li>• Added next and previous view ID buttons to the main control panel</li><li>• Added Head Track Smoothing Option</li><li>• Fixed the help text for the command SRS/X-Camera/Select_Category_n to indicate that it selects the last active camera in the category not the first category</li><li>• Fixed a bug where the command SRS/X-Camera/Select_Next_View_ID would not evaluate all cameras and would miss cameras with view IDs assigned to them</li></ul>

Table 1

## Release Notes

### 2.3.1

#### Forced FOV on a Camera

The ability to force the FOV on a camera has been around since the early days of X-Camera. The feature is not used that widely and it caused a fair amount of confusion as its implementation would not allow users to adjust the FOV in the X-Plane graphics settings without first disabling X-Camera.

The feature was causing even greater problems when people had a Multi-Monitor configuration as the implementation prevented you from having different FOV on each monitor.

With 2.3.1 we have added a setting that allows you to enable the feature. This new setting is off by default as most people don't force the FOV on the camera.

If you do use the camera FOV option you will need to enable the setting on the settings dialog. Note that if you do enable it you won't be able to reliably run a Multi-Monitor configuration that relies on different monitors having a different FOV. You will also not be able to adjust a monitor FOV in the X-Plane graphics settings without first disabling X-Camera.

## X-Plane 11.1 and Higher

X-Camera now supports the 20 quick look commands up from the 10 that were available in X-Plane versions prior to 11.1.

X-Camera also supports the additional controller slots available in X-Plane 11.1. These additional slots were needed to support view and camera position control using spare joysticks.

## Bug Fixes

- Fixed a number of UI anomalies that showed up when running in X-Plane 11.
- There was a bug where the tristate value for yoke visibility was previously being written to the camera CSV file as a Boolean (true/false) value. It is now saved properly as a 0 – 2 value but you will need to resave any camera files where a forced yoke visibility is desired.
- Fixed a long existing bug that did not reset the field of view back to the default when you had a camera selected that was using a custom FOV setting and then you selected an X-Plane view like forward with HUD. Prior to this fix the X-Plane view would have the same FOV settings as the X-Camera custom FOV setting.
- Fixed spelling error on yoke visibility legend
- Fixed the help text for the command SRS/X-Camera/Select\_Category\_n to indicate that it selects the last active camera in the category not the first category.
- Fixed a bug where the command SRS/X-Camera/Select\_Next\_View\_ID would not evaluate all cameras and would miss cameras with view IDs assigned to them.

## New Features

Head Track smoothing is now available on the settings dialog. A value between 4 and 10 will tend to smooth stutters when fast panning with TrackIR or other head tracking options.

There are now next and previous view ID buttons on the main control panel. They are located just to the right of the View ID label and are marked with left and right arrows.

## Community Airport Camera Files

The functionality for Community Airport Camera Files is still in X-Camera 2.3.1 but we have removed all references to the Community Files section on the Stick and Rudder Studios website. Since it is so easy to



automatically create airport cameras very few people have been posting them to the community section on the website.

Since sharing aircraft camera files is built directly into X-Camera and the fact that few people have been submitting their airport camera files we will be removing the community files section on the Stick and Rudder Studios website in early 2018. Please note that this action will have no impact on your ability to share aircraft camera files which is natively built into X-Camera and uses a different storage area.

## Known Problems

- We have noticed that some Carenado planes seem to have some sound anomalies with targets and potential airport cameras when you switch from a target reciprocal view to a view of the target from the plane. The Carenado sound system seems to be adjusting the engine sounds from a faraway distance to a near distance and it does not always do it very smoothly. We think this is a problem with the Carenado planes not expecting some of the camera behavior that X-Camera injects but we will continue to investigate it.
- There is a known problem with external cameras and inverted flight when the roll angle passes +/- 180 degrees. The calculated roll angle may exhibit a noticeable jump particularly if the camera is aimed straight forward. We will try to get this corrected in a future update. Note: This does not happen if it is an internal camera that you have placed external to the cockpit.

## Introduction

X-Camera is an enhanced view system plugin for X-Plane 9 or higher. With X-Camera you can define multiple view categories and multiple camera views within each category. These categories and views are unique to each aircraft allowing a high degree of customization.

The position of the camera in each view can be controlled using keyboard commands or the X-Camera control panel. After you have defined and configured all the views they can be saved to an aircraft specific CSV file in the current aircraft directory.

X-Camera also supports the creation of camera transition affects that can be used to create a series of panned views that can be executed in sequence. This is a great feature for making flight videos or setting up pre-flight inspections or fly-by scenes.

## Licensing

X-Camera is offered in both an unregistered and a registered version.

- The unregistered version currently supports all available features with the exception of saving the advanced transition features and external camera capabilities; please see the next paragraph concerning the registered version. It also supports [TrackIR](#), an integration to the [HeadShake](#) plugin V1.3 or higher from [SimCoders](#), an integration to [LinuxTrack](#) via the newest

version of the [xlinuxtrack](#) plugin, an integration to [XPRealistic](#), an integration to [SimHat](#), and an integration to the Scenic Flyer plugin.

- The registered version will allow you to save the linear and Bezier transition definitions, any advanced transition settings, and external camera definitions between X-Plane starts. It also supports Airport Camera Files and automatically generating airport camera files from your installed scenery. You can try out all of the advanced features in the unregistered version but you need to register your copy of X-Camera to save them. The following features can be saved with the registered version:
  - Linear Transition
  - Bezier Transition
  - Smooth Camera Joins
  - Auto Advance
  - Track Camera Heading
  - Track Camera Pitch
  - Level Camera
  - External Camera
  - Cineflex Camera
  - Free Camera
  - Target Following Camera
  - X-Plane 9 Chase Camera
  - Airport Cameras
  - Full set of generated airport cameras

If you are running an unregistered version of X-Camera you can still generate airport cameras from your scenery but the number of runway, starting location, and sign cameras will be limited. These generated cameras will also only be available for the current running instance of X-Plane. This will give you the ability to try out the airport camera generation feature before deciding to register X-Camera.

You can register X-Camera at <https://www.stickandrudderstudios.com/register-x-camera>. We encourage you to try out X-Camera and if you find it useful consider registering your copy.

When you have registered X-Camera we will send you a license.txt file that contains your key and email address. You may need to look in your email Spam directory as some email clients may block the email with the license file attachment. If you don't get the key in 30 minutes after registering please mail us at [Support@StickandRudderStudios.com](mailto:Support@StickandRudderStudios.com).

Simply save the license.txt file to the X-Plane/Resources/plugins/X-Camera directory. The file name is case sensitive on Linux and Mac OSX, it needs to be all lower-case.

Do not share your license key with anyone else.

## Requirements

X-Camera will run on X-Plane 9 or higher and it supports both 32 bit and 64 bit CPU architectures. Microsoft Windows, Apple Macintosh, and Linux are all supported. If you are interested in getting release updates from Stick and Rudder Studios please join our mailing list.

<https://www.stickandrudderstudios.com/mailling-list/>

## Limitations

- X-Camera only works with 3D cockpits and the free camera view of X-Plane. If you use an external camera in X-Camera in X-Plane 9, no other X-Plane views will operate until you disable X-Camera or select a non-external camera. With X-Plane 10 only the free camera view from X-Plane will be unavailable. All other X-Plane views such as chase, etc. should continue to work but without the X-Camera features.
- Generating airport cameras from loaded scenery is not supported in X-Plane 9 due to the use of scenery layout enhancements in X-Plane 10. Generated airport camera files may still work on X-Plane 9 if the scenery at that airport is compatible with X-Plane 9.
- You will not be able to change your horizontal field of view in the X-Plane rendering options while X-Camera is enabled if you have the “Enable Force FOV” setting enabled. Disable X-Camera using the X-Camera plugin menu option to adjust you default X-Plane horizontal field of view. You should also disable the “Enable Force FOV” option if you are running a Multi-Monitor configuration as you might encounter some very strange behavior.
- Mouse Look is mapped to the middle mouse button on windows when X-Camera is enabled. Using the right mouse button while X-Camera is enabled will cause X-Camera and X-Plane to fight for camera control. On Mac OSX and Linux systems X-Camera is unable to access the middle mouse button state. On these operating systems you will need to map a key or joystick button to the X-Camera middle mouse button simulation command. Please read the more detailed explanation of mouse look in the Positioning Cameras section of this manual.
- Time based camera transitions are based on the frame rate reported by X-Plane. When X-Plane is in replay mode and video recording is enabled the reported frame rate is incorrect and any time based transitions will occur very fast and not at the specified time. This problem only occurs when you are using X-Plane to capture video. Alternatively you can use a frame count for the transition or you could consider using an alternate video capture technique such as [FRAPS](#).
- If you plan on using X-Camera with [TrackIR](#) you must disable [TrackIR](#) in the X-Plane equipment settings, see Figure 1. If you don’t, X-Camera will not retrieve accurate data from the [TrackIR](#) interface.
- [TrackIR](#) is directly supported on the Windows platform via the native [NaturalPoint](#) drivers and via [LinuxTrack](#) and the [xlinuxtrack](#) plugin on Linux and Mac OSX. You must make sure that X-Camera is in the TrackIR games list if you are running on Windows. If you don’t see it, execute a

“Games Update” from the TrackIR UI.

We also know that a few users have had success with OpenTrack as it can emulate the TrackIR protocol.




Figure 1

## Optional Integrations

### TrackIR

X-Camera is built to work with Natural Point’s [TrackIR](http://www.naturalpoint.com/trackir). If you have this great product installed it can be enabled or disabled for each defined view. Please see the camera options section for more details on this feature.

X-Camera must be in the TrackIR games list. If you don’t see X-Camera in the TrackIR games list you will need to update your games from the TrackIR UI.

The TrackIR software must be running before you start X-Plane, particularly if you load a plane that has an X-Camera definition, as X-Camera will attempt to auto-enable when the plane loads and it needs to have the TrackIR software running to enable the TrackIR feature. If you forget to start the TrackIR software before X-Plane all you need to do is start the TrackIR software, disable and then immediately re-enable X-Camera. That will cause X-Camera to initialize the TrackIR interface.

If you have problems getting TrackIR to work use the System Check item in the plugins/X-Camera menu to view any diagnostic messages.

X-Camera can also accept tracking input for 3<sup>rd</sup> party solutions that don’t emulate the TrackIR interface. The datarefs and their use are outlined in the appendix under integrations.

## SimHat

SimHat is an iPhone app that allows you to use your iPhone as a head tracking device. It has functionality similar to TrackIR. You can read more about SimHat here:

<http://www.simhat.com/>

If you have configured SimHat as your head tracking device you will want to check the TrackIR head tracking option on any camera that you want SimHat input applied.

## Scenic Flyer

Scenic Flyer is a plugin that will optionally display a small GA or Glass instrument panel on the screen. This is useful if you like to fly with an exterior view but you still want to keep an eye on your speed, heading, etc. You can get this plugin from:

<http://www.digital-avionics.com/scenic/home.html>

If X-Camera detects that the plugin is installed it will allow you to control Scenic Flyer panels by camera. Please see the camera options section of this manual for more information and an image of what the Scenic Flyer panels look like.

<https://www.youtube.com/watch?v=SAp-ySvCtIc&t=5m07s>

Tutorial Link 1

## HeadShake

X-Camera is also built to work with the HeadShake plugin from SimCoders, <http://www.simcoders.com>. HeadShake monitors the g-forces on the aircraft and will “shake” the camera according to those forces. If the HeadShake plugin is installed, X-Camera will allow you to enable or disable the HeadShake effect by each camera view. Note: HeadShake only works with X-Plane 10 and above.

## XPRealistic

XPRealistic is similar to HeadShake but has even more immersive features. You can read about XPRealistic at <http://www.xprealistic.com/>. XPRealistic must be at version 1.0.6 for the integration to X-Camera to work.

## LinuxTrack

X-Camera is also built to work with LinuxTrack. The integration works very similar to the HeadShake integration where X-Camera is able to detect the presence of the xlinuxtrack plugin. If it is detected X-Camera will read the offsets published by the xlinuxtrack plugin and will apply them to the camera position if the TrackIR option is enabled on that camera.

LinuxTrack needs to be at version 0.99.11 or higher.

## Recommended Hardware

X-Camera can make extensive use of keyboard and controller button assignments to manipulate the cameras. Many of these button assignments you will do on either your yoke or joystick. We have found that a gaming mouse that has programmable buttons that can be mapped to keyboard keys adds an additional level of control in X-Camera. Figure 2 is an example of one of these gaming mice.



Figure 2

You can quickly run out of joystick buttons for all the X-Camera command actions. There are a number of optional game controllers that can significantly increase the number of buttons available. The Thrustmaster MFD Cougar Pack is one such controller.



Figure 3

## Installation

X-Camera is available as a download from [www.StickandRudderStudios.com](http://www.StickandRudderStudios.com) as well as the download area on X-Plane.org. It is packaged as a fat plugin in a zip file. Use your favorite zip utility to extract the contents of the archive into your X-Plane plugin directory. Example:

**C:\X-Plane 9\Resources\plugins**

Don't change the directory name of the X-Camera directory. It needs to be:

**Resources\plugins\X-Camera**

**Note:** If you are upgrading X-Camera to a new version we suggest the following steps:

1. Make a backup copy of your X-Camera directory
2. Unzip the downloaded X-Camera archive into a temporary directory
3. Use Windows Explorer or an appropriate file explorer for your operating system to copy the resulting X-Camera directory into your X-Plane\Resources\plugins directory, allowing the copy utility to over-write / merge the contents with the original X-Camera directory.

Using the above process will preserve your license.txt file as well as any settings and airport camera files you may have created while updating any documentation and binaries associated with the new version of X-Camera.



## Enabling X-Camera

X-Camera can be enabled or disabled from the X-Plane plugin menu or via a command assignment. When you enable X-Camera it will look for an aircraft specific camera configuration file in your current aircraft directory. If it does not find one it will create one with one category and view. The category will be named Cockpit and the one camera in that view will be called Pilot View. It will be initialized to the current pilot's head position in the 3D cockpit.

If you have multiple .ACF files in an aircraft directory you will need to create views in X-Camera for each one. X-Camera's camera coordinates are relative to the plane model's center of gravity. Since this can vary with each .ACF file we need to save X-Camera settings for each aircraft model.

X-Camera can also be enabled by selecting a specific view via a joystick button or key assignment. See the section on assigning joystick keys to specific views.

When you change aircraft in X-Plane or on the initial load of an aircraft X-Camera will see if there is a camera configuration file for the selected plane. If the configuration file is found X-Camera will auto enable and will select the first camera in the first category, normally the cockpit and the pilot view if you didn't move that camera up or down in the category. You can optionally disable this feature by checking the "Manually enable X-Camera for this aircraft" on the control panel.

**Note:** X-Camera will automatically be disabled when a new aircraft is loaded and no existing camera configuration file is found for the newly loaded plane.

## System Check

The first time you enable X-Camera we recommend running a System Check from the X-Camera plugin menu. System Check will scan your X-Plane configuration verifying that it is properly configured for X-Camera:

- Verify that TrackIR is properly configured if it is installed
- Verify the version of the HeadShake plugin if it is installed
- Check to see if the Scenic Flyer plugin is installed
- Verify that incompatible plugins are not installed or are not enabled, PilotView is an example of one such an incompatible plugin

If you come across other plugins that are incompatible with X-Camera please let us know so we can correct the problem or include them in the System Check function.

## Configuring X-Camera

After you have enabled X-Camera for the first time on an aircraft you will most likely want to define some additional categories and camera views. This can be done with the control panel which you can activate or deactivate from the X-Camera plugin menu.



If you have X-Plane Quick Look views defined for the plane, X-Camera will give you the option to import them when X-Camera is enabled for the first time on a plane that is missing the camera file. If you had a quick look view saved for the pilot view you may wish to delete the Pilot View camera that is automatically added prior to the import.

**Note:** The X-Plane chase, circle, and ride-along views do not have exact replacements in X-Camera. During import X-Camera will do the best it can to replicate those views but be aware that they do behave slightly differently.

<https://www.youtube.com/watch?v=SAP-ySvCtIc&t=5m07s>

Tutorial Link 2

## Control Panel

Figure 4 illustrates X-Camera's control panel.




Figure 4

The control panel is a window that allows you to do the following actions:

- Browse community supported aircraft camera files and import them as a base set of camera definitions
- Navigate between various categories and camera views
- Create new categories and cameras
- Insert new categories and cameras before the currently selected category or camera
- Remove categories and cameras
- Alter the names of categories and cameras

- Adjust the order of categories and cameras
- Adjust the X, Y, Z, Heading, Pitch, and Roll of the cameras
- Assign a view ID to a camera so that it can be selected with a joystick button or specific key combination
- Turn on or off features for a camera
  - Enable or Disable TrackIR (also works with LinuxTrack)
  - Enable or Disable TrackIR Limits (also works with LinuxTrack)
  - Enable or Disable HeadShake
  - Enable or Disable smooth transitions to this camera
  - Retain Mouse Look Position
  - Enable Temporary Positioning
  - Enable View Axis Input
  - Enable or Disable linear transitions to this camera
  - Enable or Disable 3D Bezier curve transitions to this camera
  - Enable or Disable auto advance to the next camera in the current category
  - Enable Camera Heading Tracking
  - Enable Camera Pitch Tracking
  - Enable Camera Leveling
  - Enable Camera Join Smoothing
  - Specify center of gravity (CG) offsets for Z,Y, and X
  - Enable External Camera
  - Enable Cineflex Camera
  - Select Scenic Flyer Panels
  - Enable Target Following
  - Enable Free Camera
  - Enable an X-Plane 9 like chase view camera

- Enable Cinema Verite for each camera
- Adjust yoke visibility on supported planes
- Toggle between editing Aircraft Cameras or Airport Cameras
- Save cameras to “X-Camera\_{*aircraft model*}.csv” in the current aircraft directory or in the case of an Airport Camera file, X-Camera/MyAirportCameras.{icao}.csv
- Restore cameras from “X-Camera\_{*aircraft model*}.csv” or the associated Airport camera file.
- Copy a single camera and then paste it over another one
- Copy the entire camera set, reload a new plane, and then paste that camera set into the plane with an option to automatically adjust the cockpit cameras.
- Snap the camera base position to the current TrackIR offsets. This lets you use your TrackIR head piece to position the view as you want it and then “snap” the camera to that position.
- Increase or decrease the distance the camera will move with each position key or button activity
- Turn Walk Mode on or off
- Set TrackIR Limits
- Enable and specify a specific field of view (FOV) for each camera if you have the “Enable Force FOV setting enabled in the settings dialog. Please read the settings section for more detail on this option and its side effects.
- Set an initial zoom factor for a camera
- Manually enable X-Camera for this aircraft. This stops X-Camera from automatically enabling when this plane is loaded. You will need to enable X-Camera manually.
- Generate Orbit and Fly-By animations
- Share your camera definition file with the X-Camera user community

## Community Camera Files

X-Camera contains a set of camera files that have been created by other users. You may want to browse those files to see if a definition exists for your particular plane or if there is one for a plane similar in size. After browsing you can load those definitions as a base for creating your camera definitions.



Figure 5

Once you have a well-defined and working definition file for a particular aircraft you can share it directly with the X-Camera user community right from within X-Camera. An internet connection is required.

Community files are stored in a local cache which is updated periodically and shipped with X-Camera. However, users are submitting new files all the time so there is the ability to refresh your local cache by clicking on the “Check for Updates” button. X-Camera will contact the community server and tell you how many files need to be downloaded and how many obsolete files should be removed from your local cache. If you confirm acceptance X-Camera will automatically refresh the local cache.

X-Camera requires an outbound internet connection to communicate with the community file server. Your firewall software may require you to grant internet access to X-Plane for this to work. Users have different preferences and may be using different default horizontal field of view settings. You will most likely need to adjust the camera definitions to suit your taste or need but the community files may help you to get started more quickly.

<https://youtu.be/vctMkivRaoo?t=587>

Tutorial Link 3

You can edit the filter field with text that will be used as a case-insensitive filter on the aircraft type and author data in the community files. This limits the list to the most likely compatible planes. You can navigate through the filtered list with the next and previous buttons. Leaving the filter field blank will show you all the community files sorted by aircraft type.

When you find the file that most closely matches your plane you can use the load button to read that camera definition file into X-Camera. There is an option called “Try Auto-Correct Cockpit” that will attempt to adjust the imported cockpit cameras using “fuzzy logic”.

### Auto Correct

Unless the community camera is an exact match of your plane and using a very similar field of view, most imported camera files need to have their cameras adjusted. The more different the plane is the more correction is required after the import.

The auto correct feature uses fuzzy logic in an attempt to automatically adjust cameras that appear to be cockpit cameras. The standard convention in X-Camera is to have the first category be for internal cockpit cameras and for the very first camera in that first category to be the default pilot view. As a matter of fact, when you enable X-Camera for the first time it automatically creates that category and camera.

The auto correct feature relies on people sticking to the convention that any shared files have the pilot view and in the first category and camera. Furthermore, it relies on that same condition being setup in X-Camera before trying to load a camera file.

Using the above, assumption X-Camera compares the difference in X, Y, and Z coordinates of the pilot camera in X-Camera prior to the load and those same coordinates with the pilot camera in the community file. X-Camera then calculates the necessary offsets that would need to be applied to the community file to get the pilot close to where the cockpit is for the loaded plane.

Next, X-Camera searches for other internal cameras in the community file that are within five meters of the pilot view camera. The assumption is that all of these are likely cockpit cameras and they should have the same offsets applied to them. X-Camera then adjusts those cameras so they will be placed and similarly aligned to the original pilot camera.

The process is not perfect but it does a reasonable good job of getting the cockpit cameras very close to where they should be. After loading a plane using this features we suggest that you review all the cameras before saving the file. If you don't like them you can restore the original camera definition and then try another community file that may be closer to what you need.

The auto adjust feature will not touch any external cameras or any other internal cameras that are more than five meters from the pilot camera in any coordinate direction. These cameras will need to be adjusted by hand.

**Note:** The Auto Adjust capability is also available when you paste a camera set from the control panel.

## Sharing Your Camera Definition

After you have a well-defined and working camera file we encourage you to share it with the community. This is particularly useful if you find that the existing community files are lacking in support for your favorite plane or if you added significant functionality to the definition with more views and cool transitions like walk-around inspections.

You can share your definition directly from the main control panel using the "Share Camera File with Community". When activated, this capability will show you how many files have already been submitted to the community for the current aircraft loaded. If you do choose to share the file you will need to fill in the author and version fields on the main control panel. It is perfectly acceptable to use a pseudonym for the author. We recommend using a date for the version. Keep in mind that shared camera definition files are just text files and are easily read and open to the public. Although it is unlikely you would do this, we do want you to be aware of any personally identifying information you might put in category names, camera names, author, version, and target name fields. All other data in the file is simply numeric in nature.

After the file is shared X-Camera will remember the version and present you with an opportunity to update the shared file with a new version later when you make enhancements. If you do update the file you will need to change the version. Your old version will be deleted from the community server and other user's local cache when they do an update.

You will need to use the "Check for Updates" button on the Browse Community Dialog to update your local cache with your submission and any others that have been done since your last refresh.

## Adding Cameras and Categories

The control panel buttons add, Ins, and delete will allow you to create new categories and cameras. When you create a new category X-Camera will automatically clone the current camera and add it as the first camera in the category. The added category and camera will be given assigned names based upon their position in the category/camera tree. You can now change those names and position the new cameras to your liking.

Adding a camera to an existing view is similar to adding a new category. Select the category you want to add a camera to. Select a camera that is close in position to the new one you want to create and press the add button in the camera selector area. The current camera will be cloned and added to the category. You can now change the name of the camera and adjust its position.

Cameras and Categories can be inserted prior to the current camera or category by using the Ins button.

Categories and cameras can be moved up or down in their slot by using the move up and down buttons.

Cameras or categories can be deleted but there needs to be at least one camera in a category and at least one category left. X-Camera will not allow you reduce the category and camera count to zero.

**! Don't forget to save your cameras.**

## Positioning Cameras

All cameras, except the free camera, are attached to the plane. This means that if the plane moves the camera moves with it. All camera positions are relative to the plane's center of gravity (GC).

Just because a camera is attached to a plane does not mean you can't move it a significant distance from the plane. You can use this, along with walk mode, to explore the exterior of the plane and its surrounding's including gate equipment and airport structures.

Cameras can be positioned with the control panel, the keyboard, the mouse, or any combination of the three. The size of the movement will depend on the current movement range setting, small, medium, large, or very large and the movement command modifier, slow or fast. The values for each of these settings can be adjusted using X-Camera's plugin menu settings option.

A Free camera is not attached to the plane. As soon as you check the free camera checkbox in the control panel the camera will be “dropped” at the plane’s current location in the world. The camera will not move when the plane moves.

The X-Plane 9 chase view camera will only allow you to move the camera nearer or farther along the long axis of the plane. Left, Right, Up, Down, and Pitch are locked on this type of camera.

## Keyboard Control

X-Camera uses the same positioning commands as X-Plane. Assuming that you have not re-mapped the default keys, Table 2 shows the keyboard assignments for moving the camera. Note: the slow commands are not available on X-Plane 9 and Page Up / Down and . / , mappings vary by operating system.

Key	X-Plane Command	Action
→	sim/general/right	Move the camera to the right
←	sim/general/left	Move the camera to the left
↑	sim/general/up	Move the camera up
↓	sim/general/down	Move the camera down
Page Up or .	sim/general/forward	Move the camera forward
Page Down or ,	sim/general/backward	Move the camera back
Shift →	sim/general/right_fast	Move the camera to the right quickly
Shift ←	sim/general/left_fast	Move the camera to the left quickly
Shift ↑	sim/general/up_fast	Move the camera up quickly
Shift ↓	sim/general/down_fast	Move the camera down quickly
Shift Page Up or .	sim/general/forward_fast	Move the camera forward quickly
Shift Page Down or ,	sim/general/backward_fast	Move the camera back quickly
Ctrl →	sim/general/right_slow	Move the camera to the right slowly
Ctrl ←	sim/general/left_slow	Move the camera to the left slowly
Ctrl ↑	sim/general/up_slow	Move the camera up slowly
Ctrl ↓	sim/general/down_slow	Move the camera down slowly
Ctrl Page Up or .	sim/general/forward_slow	Move the camera forward slowly
Ctrl Page Down or ,	sim/general/backward_slow	Move the camera back slowly
Q	sim/view/pan_left	Rotate left
E	sim/view/pan_right	Rotate right
S	sim/view/pan_down	Pitch down
No Default Key	sim/view/pan_up	Pitch up
Ctrl +	N/A	Increase the movement increment
Ctrl -	N/A	Decrease the movement increment
Ctrl HOME	N/A	Puts the camera back to its original position in the 3D cockpit prior to enabling X-Camera
Ctrl DELETE	N/A	Zeros the camera's pitch angle
Ctrl END	N/A	Zeros the camera's heading relative to the plane's centerline

Table 2

The camera position will continually move as long as the key is depressed. Movement will stop when the key is released. The amount of distance is controlled by the Ctrl +/- keys or their corresponding control panel buttons. The distance increments are small, medium, and large. Each increment has a fast, normal, and slow setting that can be mapped to X-Plane's fast/normal/slow movement and panning commands. Note, X-Plane 9 does not have slow movement commands.



**Tip:** Keyboard input is not accepted for camera movement if the focus is one of the text edit fields of the control panel, category name, camera name, View ID, etc. Simply click anywhere else in the control panel to defocus the edit field then keyboard input will be directed to X-Plane so you can move the camera with your keys.

**Tip:** If you are trying to position an external camera that is some distance away from the aircraft's center of gravity you may need to put the positioning system into the larger range using the <CTRL> + key combination. It is hard to see the changes when the range is set to small or medium when the camera is a long distance away from the plane.

**Tip:** Due to some recent changes in X-Plane a conflict arose around the X-Plane general\_up and general\_down commands with regard to using these to respond to ATC. X-Camera has these commands mapped to camera move up and down and was intercepting the commands when the ATC window was open. There is an option in the settings dialog that allows you to lock out keyboard control for camera movement when the X-Camera control panel is not open. When this option is set you will not be able to move the camera with the keyboard if the control panel is not open but the commands will go to the ATC window restoring the ATC response functionality. See the settings section of this manual for more information.

X-Camera also supports many of the built in X-Plane view commands such as "sim/view/left\_up", "sim/view/glance\_right", "sim/view/right\_135", etc.

## Mouse Move and Mouse Zoom

Cameras can be placed using a feature very similar to mouse look. Before you can use this feature you must map keys or joy stick buttons to the following X-Camera commands:

```
SRS/X-Camera/MouseMove_X_Y  
SRS/X-Camera/MouseMove_X_Z  
SRS/X-Camera/MouseMove_Heading_Pitch  
SRS/X-Camera/MouseMove_Zoom
```

Pressing and holding down the key or button mapped to a mouse move axis will activate the feature. You can then move your mouse to position the camera along the two axis associated with the command. Releasing the key or button disables mouse move.

To adjust the camera left-right / up-down, press and hold down the key or button mapped to the MouseMove\_X\_Y command. While the key is held down, move the mouse to adjust the camera's position. How far the camera moves will depend on the mouse movement and the current range setting in effect.

Use the key mapped to MouseMove\_X\_Z to use the mouse to move the camera left-right / forward-back. Use the key mapped to MouseMove\_Heading\_Pitch to rotate and pitch the camera left-right and up-down.

Mouse Zoom is only available on external cameras and is an alternative to using the mouse scroll wheel. Use the key mapped to MouseMove\_Zoom. While holding down the key move the mouse forward and backward to zoom in and out.

**Tip:** Investing in a gaming mouse that has additional buttons that can be mapped to keystrokes can enhance camera control by allowing you to map mouse move, mouse look, mouse zoom, and camera centering commands to the additional mouse buttons. See Figure 2.

<https://www.youtube.com/watch?v=B02dbKir2oo&t=22m40s>

Tutorial Link 4

## Field of View

If you enabled the “Enable Force FOV” setting in the settings dialog you will see additional controls displayed on the control panel. With these controls you can enable each camera to have a specific horizontal field of view (FOV). This is accomplished using the FOV slider on the left hand side of the control panel and the FOV enable checkbox. When the checkbox is enabled you can set the FOV from 15° to 170° for each camera using the slider and the slider arrow buttons. When the FOV checkbox is disabled the camera will use the FOV setting in X-Plane’s rendering options at the time X-Camera was enabled.

If you have the setting option “Enable Force FOV” enabled you will not be able to change your horizontal field of view in the X-Plane rendering options while X-Camera is enabled. Disable X-Camera using the X-Camera plugin menu option to adjust your default X-Plane horizontal field of view. You also can not reliably run an X-Plane 11 Multi-Monitor configuration as each monitor may require a different FOV.

## Initial Zoom Factor

Each camera can have an initial zoom factor. The default is 1.0. You can set the zoom factor in the control panel by first selecting the camera you want to adjust, then zoom the camera in or out using the = / - keyboard keys or any joystick buttons you have assigned to X-Plane’s zoom commands. Once you have the zoom where you want it, click the “Set Initial Zoom” button in the control panel. When this camera is selected in the future the zoom factor will be initially set to this value.

Removing the zoom factor from a camera is accomplished by zooming the camera all the way out using the – keyboard key and then clicking the “Set Initial Zoom” button.

**Note:** The current version of X-Camera does not support transition animation of the zoom setting between cameras. We will look at adding this to a future version of X-Camera but due to the architecture of the SDK’s camera support animation of differing zoom factors between cameras may not be possible.

## Panning

X-Camera will work with your HAT switch. X-Plane supports a four position HAT switch. You can map your HAT switch to X-Plane's panning commands and X-Camera will respond accordingly. X-Camera also has a few extra features that you may find useful.

- Pan speed toggle is an X-Camera command that can be mapped to a joystick button or key press. When activated, X-Camera will increment the panning speed from slow, to normal, to fast, and back to slow within the movement ranges of small, medium, and large. This allows you to have one hat switch that can support both fast and slow panning.

Pan speed toggle only works if you have it enabled in the settings menu. When disabled your pan commands will react according to the pan speed command to have it mapped to, i.e. `sim/view/pan_left_slow`, `sim/view/pan_left`, `sim/view/pan_left_fast` for X-Plane 10.

- Eight-way hat switch support can be used with X-Camera by mapping your eight-way 45° HAT switch buttons to X-Camera's pan commands, `SRS/X-Camera/Pan_Left_And_Up`, etc. If you want your HAT switch to work with X-Plane's four-way panning support we suggest mapping the 0°, 90°, 180°, and 270° pan commands to X-Plane's pan commands and map the 45° commands to X-Camera's commands. This will allow your HAT switch to work with X-Plane when X-Camera is disabled.

The camera can also be panned using X-Plane's view axis. Many joystick controllers will have a spare rocker or other axis that can be assigned to the left/right up/down view axis. If you have assigned a joystick axis to the view control in X-Plane, X-Camera will use it to rotate the camera left/right and up/down. Use the Enable View Axis Input checkbox on the control panel to enable this feature for each camera.

**Note:** this is disabled if you have TrackIR enabled for a camera.

You must assign the view axis before you enable X-Camera. If you need to alter the axis assignment disable X-Camera, make the change, then enable X-Camera. This procedure is also needed for axis calibration. Calibration must be done with X-Camera disabled.

## Mouse Look

X-Plane supports panning the camera using a right mouse click. Due to some limitations in the X-Plane SDK it was not possible to get X-Camera to respond consistently to the right mouse click across all platforms, Windows, OSX, and Linux. For this reason X-Camera uses the middle mouse button on Windows to activate mouse look. On a Mac or Linux PC there is an X-Camera command that can be mapped to a key or a joystick button to simulate a middle mouse button.

While mouse look is enabled the camera's heading and pitch can be adjusted with mouse movement. There is an optional camera setting that retains the mouse look position when the middle mouse button is released or a simulate middle mouse command is completed. Normally the camera will revert to its original position when mouse look is ended. Mouse look is disabled when TrackIR is enabled on a camera.

**Note:** Some aircraft designers use a right mouse click to actuate knobs; the JarDesign A330 is one example of this. You can use a right click to activate controls but any attempt to pan the camera with mouse movement will cause X-Camera to fight that movement. In newer version of X-Plane a right mouse double click will cause X-Plane to enter a continuous mouse look state. Try to avoid this as X-Camera and X-Plane can be in a continuous fight mode. If you do inadvertently get into this state just do a single right click which will take X-Plane out of mouse look mode.

## Walk Mode

Walk Mode is a lot like playing the late 1970's arcade game Asteroids. The mode is enabled or disabled by mapping a key or button to the X-Camera command, "SRS/X-Camera/Toggle\_Walk\_Mode", or its associated control panel button. When in walk mode any of the position keys will start the camera moving in that direction. If you press the same key again it will move in that direction even faster. If you push the opposite position key it will slow or halt the previous movement depending on how many times you press.

Movement input is always based on the camera's current heading. As an example, if you start moving forward, then rotate the camera 90 degrees to the right and then press the forward key the camera will move forward and right at the same time.

Walk mode can be stopped by pressing Ctrl Space again. It will also be automatically disabled if you move to a different view. You can also map a joy stick button to the SRS/X-Camera/toggle\_walk\_mode command.

Walk mode will also take input from a mouse move gesture.

You can get some pretty interesting camera movement with this mode and once you get proficient at it you can use it to do external preflight inspections or explore an airport's structure. The mode can be a bit sensitive. Particularly when you use large movement increments or you have entered numerous movement inputs at different angles. We recommend using it with the small movement increment, <CTRL> – will decrement the movement range.

## Camera Positioning with a Spare Joystick Controller

Cameras position, heading, and pitch can be adjusted by mapping a spare joystick / game controller to X-Plane's camera and view axis and by enabling Camera Axis Input on a specific camera. The following table outlines how the camera will behave based on the specific axis input.

X-Plane Axis	Camera Behavior
<b>View Left / Right</b>	Camera heading is adjusted left or right
<b>View Up / Down</b>	Camera pitches up or down based
<b>View Zoom</b>	Camera zooms on external cameras
<b>Camera Left / Right</b>	Camera moves left / right of its current heading
<b>Camera Up / Down</b>	Camera moves up / down based on its current heading and pitch
<b>Camera Zoom</b>	Camera moves forward or backward of its current heading and pitch

You must enable the checkbox “Enable Camera Axis Input” in order for X-Camera to respond to these axis inputs. You can also toggle this checkbox on or off by mapping a key or joystick button to the command “SRS/X-Camera/Toggle\_Camera\_Axis\_Input”.

After selecting a new camera with the axis input enabled you will need to move the controller slightly to start getting input. Once the axis is returned to center camera movement will cease. The speed of camera movement is based on the amount of axis deflection as well as the current movement increment setting for the camera.

It is entirely possible to map an axis to a joystick axis that is not spring loaded. An example of this might be to map the Camera Up / Down axis to a throttle lever. These are typically not spring loaded so the center of travel must be found by feel. This is one of the reasons why we may not always want to be accepting axis input and why there is a checkbox to turn it on and off. If such an axis is not dead center the camera will just start moving.

Make sure the joystick you are using is properly calibrated. X-Camera depends on this calibration to know where the center travel is for a joystick. There is a built-in +/- 2.5% null zone around any axis meaning you will need to move the stick slightly off center to get the camera to move.

You can also specify a view axis smoothing factor on the settings dialog. You may find value of 4 – 10 for view axis smoothing will help smooth out noisy joystick controllers.

Some spring loaded joysticks axis may not be at a perfect center position when released. This can cause camera drift when accepting camera axis input on a camera. This can be corrected by activating the view axis calibration item in the X-Camera plugin menu. The calibration process is similar to the one it X-Plane. Simply follow the instructions in the dialog.

At the end of the process you will have an opportunity to adjust the null zone for the camera / view axis. A larger null zone will compensate for slop at the center position. Note, that the larger the null zone is a larger the joystick movement will be required to initiate camera movement.

<https://www.youtube.com/watch?v=SAP-ySvCtIc&t=5m07s>

Tutorial Link 5

## Snap to TrackIR

This control panel button allows you to position a camera view using TrackIR head movement. When the view looks the way you want after positioning your head simply click on this button and the current TrackIR position will be the new camera base position.

## Camera Options

### TrackIR

TrackIR from Natural Point is a unique device that tracks the movement of your head using a camera and either a reflective device or set of active LEDs that you attach to your headset or a hat. X-Camera can accept input from TrackIR and add the current head position offsets to the camera’s base position. Using TrackIR you can look around the environment very naturally.

TrackIR can be turned on or off for each camera. The reason you might want to do this is if your camera definition is a close-up of an instrument panel. By disabling TrackIR input for this camera you can have a very stable view which eliminates any head movement so you can easily use the mouse to activate cockpit knobs and switches.

X-Plane also supports TrackIR for its 3D cockpit view. However, you cannot have TrackIR enabled for both X-Plane and X-Camera simultaneously. Disable the TrackIR equipment option as shown in Figure 1 when you plan on using X-Camera for all your 3D views.

You need to make sure that you get the latest Game Update by using the associated menu action in the TrackIR control panel, see Figure 6. Verify that you see X-Camera in the title list after getting the Game Update. The TrackIR software must be running before you start X-Plane. If you forget to do that you will need to disable and then re-enable X-Camera after you have started the TrackIR software.

TrackIR is likely going to need some tuning to make the head movement smooth. In the Motion Control box in Figure 6 you will find the speed and smooth settings. You will need to spend some time experimenting with these settings to get a smooth but responsive experience with TrackIR. The settings of 1 for speed and 12 for smooth seemed to work well with our rig.

There is also a head track smoothing factor that can be specified on the settings dialog. A value of 4 – 10 may help smooth out stutters when panning with your head quickly. Higher smoothing factors will inject a lag that you may find unacceptable.

**Note:** Native TrackIR support is only available on the Windows platform; however, you can use LinuxTrack to extend support to Linux and Mac OSX. LinuxTrack needs to be at version 0.99.11 or higher.




Figure 6

## Limit TrackIR

This option works in conjunction with TrackIR. You can set min/max X,Y, and Z camera limits which will prevent TrackIR or LinuxTrack head movements from positioning the camera outside the limits. This is useful when you have a TrackIR enabled cockpit camera and you don't want the pilot to be able to stick his/her head outside the hard cockpit walls or past the seat head rest.

You must set the limits using the TrackIR limit buttons, Max Left, Max Right, etc. To do this, first disable the Enable TrackIR Limits checkbox. Position the camera either using the positioning keys or with your head movement to the far left edge of cockpit. Press the Max Left button. Repeat this for Max Right, Max Forward/Back, and Max Up/Down.

Now click the Enable TrackIR Limits checkbox. You should not be able to position the camera outside of these limits using TrackIR or LinuxTrack. Don't forget to save your camera settings.

**Tip:** The limits are oriented with you facing forward. If you happen to have a camera that is facing the rear of the aircraft, i.e. a rear facing cabin camera, you need to remember that the left limit is now really your right limit and the forward limit is really your back limit.

**Note:** When TrackIR limits are enabled it does not prevent the camera coordinates from being positioned past the limits with walk mode or the movement commands, however, the camera view will be restricted.

## HeadShake

HeadShake is a cool plugin from SimCoders that monitors the G-Forces on your aircraft and will inject camera shake to simulate the head movement you would experience during a hard landing or turbulence. Stick and Rudder Studios collaborated with SimCoders to make our two plugins work together.

You need to install HeadShake version 1.3 or higher. Note: that as of this writing HeadShake only supports X-Plane 10 and above not X-Plane 9. If you enable HeadShake for a specific camera then X-Camera will add any calculated offset from HeadShake to the camera's base position. It also adds in anything from TrackIR if that is enabled.

HeadShake was unable to support TrackIR directly so now you can get the best of both worlds by using them together with X-Camera.

## Enable XPRealistic

XPRealistic is a commercial lua script that is similar to HeadShake but more expansive in its immersion options. If you have XPRealistic installed and you want to have the camera effects added to this camera then enable this checkbox. You must be running XPRealistic version 1.0.6 or higher for this option to work.

**Note:** The XPRealistic and HeadShake options are mutually exclusive. You cannot have both enabled at the same time on the same camera.

## Smooth Transition

The smooth transition camera option will cause the camera to smoothly transition from a previous camera view to this one over roughly 500 milliseconds, or 15 frames by default. If you want the transition to last longer specify a transition frame count. Transitions only work within a view category as the affect is pretty strange going from an external camera to a say a cockpit camera.

The smooth transition follows a sine wave from 0 to 180 degrees. This results in a transition that starts slow, peaks at the mid-point, and then slows down toward the end.

## Retain Mouse Look Position

If the Retain Mouse Look Position option is enabled the camera's base position will be updated to the mouse look position when mouse look is toggle off. If this option is disabled the camera will revert back to its original orientation prior to activating mouse look.

There is an X-Camera command, "SRS/X-Camera/Restore\_Current\_Camera\_Position" that can be mapped to a joystick button that will allow you to restore a camera to its previously saved position.



**Note:** Mouse Look mode is disabled if TrackIR is enabled and the TrackIR hardware has been detected. This is done so that your head movement and mouse movement don't fight each other

## Enable Temporary Positioning

With this option enabled the camera will not retain position changes if you move off the camera and select a different view. This is particularly useful when you want to use mouse look or walk mode to move the camera around but you would like the camera to revert back to its original orientation as soon as it is deselected.

## View ID

The view ID is a positive number you can assign to this particular view. It is used to map joystick buttons to select specific views, see Figure 12.

Although we only allow you to map view IDs 1-25 you can assign higher ID numbers. We might add more mappings in the future but 25 seemed like a pretty good number to start with.

View ID numbers 1 through 25 map directly to the X-Camera commands:

SRS/X-Camera/Select\_View\_ID\_1 through SRS/X-Camera/Select\_View\_ID\_25

As an example if you place the 1 in the View ID field of the pilot camera you can then map a keyboard key or joystick button the command SRS/X-Camera/Select\_View\_ID\_1. When that key or button is pressed the pilot camera will be selected regardless of the current category or camera.

The section of the manual concerning joystick button assignments shows you how to create these mappings. There is also a section of the tutorials that illustrate this.

<https://youtu.be/vctMkjbRaoo?t=200>

## X-Plane Quick Look Emulation

X-Camera also has the ability to use the View ID concept by emulating the X-Plane quick look functionality. X-Plane quick look allows you to save and recall later up to ten views, 2- in X-Plane 11.1 and higher. The commands to do this are typically mapped to the numpad on your keyboard. Note that it is possible to map those commands to other keys. The <ctrl> key is used as a modifier to indicate that a view should be saved.

X-Camera will respond to these X-Plane commands and use the view ID concept to emulate the quick look function. View ID 1 – 10 will be used to emulate quick look keys 0 – 9 in X-Plane release below 11.1. X-Plane 11.1 and higher support 20 quick look commands which will use View ID 1 – 20.

<https://www.youtube.com/watch?v=SAp-ySvCtIc&t=5m07s>

Tutorial Link 6

## Linear Transition, Bezier Transition, Auto Advance, Transition Frames, and Tracking Options

These options make up the Advanced Transition features of X-Camera. They are discussed in the Advanced Transitions section of this manual.

### Advanced Transitions

X-Camera supports the definition of advanced transition affects that can be used to create a number of cool camera affects. Here are a few examples of what this feature can be used for.

- Creating linked transitions that will simulate an external pre-flight inspection of the aircraft
- Create very smooth and slow transitions that can be used to create dramatic camera panning affects for making slick flight videos
- Create transitions for unique spot views and fly-bys of the aircraft

Advanced transitions are created using the following options on the X-Camera control panel:

- Enable Linear Transitions
- Enable Bezier Transitions
- Auto Advance to the next Camera
- Transition Frame count
- Smooth Camera Joins
- Track Camera Heading
- Track Camera Pitch
- Level Camera
- Center of Gravity (CG) offsets
- Hidden Camera

[https://www.youtube.com/watch?v=Q7C0\\_D2jgEU](https://www.youtube.com/watch?v=Q7C0_D2jgEU)

Tutorial Link 7

### Enable Linear Transition

When this option is enabled the camera will transition from a previous camera position in the same category to this camera over the number of frames specified by the Transition Frame Count. The difference between previous and new camera coordinates for X,Y,Z, Pitch, and Heading are divided by the Transition Frame Count. Then, as X-Plane renders each frame, the camera will be moved by the divided increment for each coordinate point. The result is some pretty cool panning affects.

### Enable Bezier Transition

Bezier transitions will join 3 – 32 cameras using a 3D Bezier Curve algorithm. The result will be an ultra-smooth animation of joined cameras with no discernable stitch at the join points. You need a minimum of three cameras to make a Bezier transition work, a starting camera, a set of middle cameras that all have the auto-advance and Bezier Transition options set, and an ending camera that has the Bezier

transition option set and either no auto advance or an auto advance to either a linear or smooth transition.

The transition frame counts of all the Bezier enabled cameras will be added to create one continuous frame buffer that the 3D Bezier routine will use for its output. If you do not specify a frame count for a camera or a frame count below ten then ten frames will be used at that transition point.

The 3D Bezier routine will calculate X, Z, and Y points for the camera over the total frame count. Camera heading and pitch between cameras uses a linear transition algorithm between cameras. As an example, if camera one has a heading of 000 and camera two has a heading of 045 and a transition frame count of 100 then the camera's heading will be adjusted .45 degrees to the right over 100 frames. The same approach is used for camera pitch transitions between cameras.

The animation of a Bezier transition cannot be seen with the control panel open and the "Allow Auto Advance" checkbox in the lower left corner of the control is not checked. This allows you to step through each camera in Bezier transition set and make changes to the camera without the animation automatically starting and preventing individual camera editing. If you want to see the full animation simply check the "Allow Auto Advance" checkbox. Bezier transitions will always work if setup properly when the control is not being displayed.

<https://www.youtube.com/watch?v=B02dbKir2oo&t=7m08s>

Tutorial Link 8

## Transition Frame Count

The transition frame count specifies how many X-Plane rendering frames it takes to complete a linear or smooth transition. You can roughly calculate the number of frames needed based on how long you would like the transition to take and what your average X-Plane frame-rate is. As an example, suppose you would like a transition to take roughly 10 seconds and your average frame-rate is 30 FPS. Then you want to set your frame count to 300.

## Transition Seconds

You can optionally specify the number of seconds you want a transition to occur. If transition seconds are specified then this will over-ride the frame count. X-Camera will calculate the required number of transition in real-time based on the simulator's frame rate at the time the transition is started.

**Note:** the transition seconds option will assume a 30 FPS frame rate if the simulator is paused.

## Enable Auto Advance to the Next Camera

This allows you to link cameras in the same category together into one continuous animation cycle. When this is enabled on a camera and the next camera in the category has either smooth, Bezier, or linear transition enabled, the view will automatically advance to the next camera in the sequence as soon as the transition to this camera is completed.

The auto advance feature is disabled whenever the X-Camera control panel is being displayed. This helps prevent endless animation loops where all cameras have auto advance set with the next camera having

a transition option. This also allows you to manually advance through the sequence using the next and previous camera buttons on the control panel and make changes to each step without having to wait for the entire sequence to complete. As soon as you close the control panel window the auto advance option will be re-enabled. You can enable the “Allow Auto Advance” option in the lower left corner of the control panel to temporarily allow auto advancing while the control panel is open.

## Smooth Camera Joins

Smooth camera joins works in conjunction with the smooth and linear transitions and the auto advance feature. When this option is enabled X-Camera will create a Bezier curve around the camera join points. The curve is defined by the “Camera Smoothing Window” which defaults to 60 frames.

A three point Bezier curve is created 30 (half of 60) frames before and after the join point which will result in a smoother transition.

The Camera Smoothing Window can be adjusted to a higher value in the Settings Dialog.

## Tracking Cameras

There are four flavors of tracking cameras:

- Track Heading
- Track Pitch
- Level Camera
- Target Following Camera

A tracking camera will automatically calculate the camera heading, pitch, and roll to keep the camera pointed at the plane’s center of gravity (CG). Let’s look at each one individually.

### Track Heading

With this option enabled the heading of the camera will automatically be adjusted to keep the camera’s heading pointed to the plane’s center of gravity. The CG point varies from aircraft to aircraft but it is typically near the wing and toward the center of the fuselage. You can adjust the CG for any camera by enter numbers in the Z and Y CG offsets fields. These offsets are roughly in meters.

If you want the camera to track a little further forward than the default CG put a negative number in for the Y offset.

### Track Pitch

With this option enabled the pitch of the camera will automatically be adjusted to keep the camera’s pitch pointed to the plane’s center of gravity. Similar to the track heading option above you can adjust the pitch focal point for a camera by enter numbers in the Y CG offsets fields. If you want the camera’s pitch to be a little higher put a positive number in the Y field.

### Level Camera

Think of an external camera as if it were attached to a pole that is welded to the plane's fuselage. As the plane pitches and rolls the camera's elevation, pitch, and roll angles will be adjusted. The further away the camera is from the plane's center of gravity the more pronounced the elevation change will be.

The level camera option has the effect of attaching the camera pole to the fuselage using a gyro stabilized gimbal mount. This means that as the plane pitches and rolls the pole will stay level with the ground. The camera's pitch and roll angles can still be controlled independently.

The level camera option is primarily designed to work with external cameras. It is still available with an internal camera but its functionality is more limited and it is mutually exclusive with the track pitch option when used with an internal camera i.e. External Camera option NOT set.

### *Cinema Verite*

If you enable this option the X-Plane Cinema Verite option will be enabled. This gives the camera a hand-held effective by injecting a slight wobbling of the camera. This probably makes the most sense for cabin cameras that are looking out the window to simulate a passenger filming with a hand held video camera. This option only works with internal cameras.

### *Target Following Camera*

A target following camera will track a predefined target defined by a latitude, longitude, and elevation in meters. Targets and target following cameras are explained in detail in the targets section of this manual.

### *Hide Yoke*

There is an X-Plane dataref that most planes will honor that controls the visibility of the yoke. The dataref documentation is a bit ambiguous so some aircraft developers interpret its value a little differently. Setting it to one or zero could mean hidden or shown, it is dependent on the aircraft so some experimentation is needed. Furthermore, some aircraft don't even look at this dataref so it is not guaranteed you will always be able to control the yoke visibility with this.

The feature is implemented as a tri-state option. Each time you press the button the state will cycle through the three states and the button text will be updated with the current state. These are the states:

- Don't Force – In this mode X-Camera will make no attempt to modify the yoke visibility dataref. Its state will be governed by X-Plane and the aircraft model.
- Force to zero – In this mode X-Camera will write a zero to the dataref. This may either hide or show the yoke based on the plane's model.
- Force to one – In this mode X-Camera will write a one to the dataref. This may either hide or show the yoke based on the plane's model.

<https://www.youtube.com/watch?v=SAP-ySvCtIc&t=5m07s>

Tutorial Link 9

## Hidden Camera

Some camera animations can have multiple cameras joined together with auto advance to make a complete animation. The Orbit animations described in the following paragraph use such a technique. In this situation you typically are interested in the first camera in sequence to initiate the animation either by selecting it in the mini-control panel or by a next / previous camera command.

The hidden camera option tells X-Camera to NOT display the camera in the mini control panel and also to skip it when using a next and previous camera command when the main control panel is closed.

**Note:** You do not want to hide the starting camera in a sequence.

## Automatically Creating Orbit and Fly-By Animations

X-Camera can generate categories that are populated with orbit or fly-by animations based on some user provided parameters. Each orbit or fly-by will be placed in its own category based on the name of the orbit or fly-by name.

<https://www.youtube.com/watch?v=B02dbKir2oo&t=15m13s>

Tutorial Link 10

You can start the generation by pressing the “Create Orbit” or “Create Fly-By”, see Figure 4. The following figures illustrate the additional parameters you will provide to create these animations:

Parameter	Create Orbit	Create FlyBy
Name	Orbit_1	FlyBy_1
Initial Camera Heading	270.00	Camera Attack Heading: 170.00
Radius in Meters	10.00	Initial Height in Meters: 25.00
Min Height in Meters	-3.00	Distance in Meters: 500.00
Max Height in Meters	3.00	CPA X in Meters: 50.00
Duration in Seconds	30.00	CPA Z in Meters: -10.00
Reverse Rotation	<input type="checkbox"/>	CPA Y in Meters: 10.00
Continuous	<input type="checkbox"/>	Duration in Seconds: 30.00
Buttons	Cancel, Create	Cancel, Create

Figure 7

## Orbit Parameters

- Name is used to create a category of that name and each camera in the category will use this parameter as the first part of the camera name with a – n appended where n is the camera number in the sequence.
- Heading is the starting angle of the camera. The nose of the aircraft is a 360 so in the example above the camera starts the orbit on the right side of the aircraft facing to the plane's left.
- Radius is how far away the camera is from the center of gravity of the plane. You will need to increase this number for large jets.

- Min and Max height specify how high the camera will be placed in the orbit during the cycle. If min and max are the same value the camera will remain at that height offset throughout the rotation. If min and max are different the animation will oscillate from the mid-point to max, to mid-point, to min, and then back to mid-point.
- Duration is specified in seconds and will determine roughly how long the orbit will last.
- Reverse rotation will cause the animation to occur in the opposite direction of rotation
- Continuous will allow the orbit to repeat itself up to approximately 60 times before stopping

When you press the create button on the dialog X-Camera will create the category and populate it with the cameras. If you do this multiple times with the same name the existing category will have its cameras replaced with new ones.

### *Fly-By Parameters*

- Name is used to create a category of that name and each camera in the category will use this parameter as the first part of the camera name with a – n appended where n is the camera number in the sequence.
- Attack Heading specifies the camera heading as it approaches the aircraft. The example of 170 degrees has the camera starting the Fly-By off to the left of the plane
- Initial Height is the camera's height above the plane's current altitude.
- Distance specifies how far away the camera is at the start of the fly-by.
- CPA X, Y, and Z specify the closest point of approach (CPA) between the camera and the aircraft. If you specify 0,0,0 then the camera will pass directly through the aircraft's center of gravity. These three coordinates allow you to specify where the camera will be when it passes the plane at its nearest distance. Positive X will be off to the right of the plane, positive Y will be above the plane, and positive Z will be behind the plane.
- Duration specifies roughly how long the fly-by will last.

You can create additional orbits and fly-bys by just specifying a different name. Then only limit is the number of categories.

### *Some Notes on Advanced Animations*

- Transitions only work between cameras in the same category. The reason for this is to prevent some strange animations between cameras from very differing categories, as an example, when switching from interior to exterior views.
- Pressing any positioning key in the middle of a transition will cause the transition to stop at the final camera position.
- Avoid creating endless loops in a camera category. Do this by making sure that at least one camera in the category does not have auto advance enabled or at least one camera has neither linear nor smooth transition enabled.
- Mouse look and TrackIR will continue to work during transitions but panning with the HAT switch is disabled until the transition is complete.

- High values in the Transition Frame Count are going to cause the transition to take a long time to complete. We do not restrict high values but it is unlikely you will need anything over 1,000 frames. Conversely, very low values, below 10 as an example, may make the transition appear immediate.
- Transitions between cameras with different tracking options will likely result in some abrupt changes at the beginning and end point of the transitions. For fluid transition between cameras it is recommended to keep the tracking options similar.
- Tracking cameras are generally not used in the cockpit; they were primarily designed for external views. Although they work, they produce some pretty odd results.
- When the tracking options are enabled the camera's heading and pitch will be updated. As you try to position the camera with the keyboard a new heading and pitch will be calculated affecting the next camera movement. This can cause very confusing movement when using the positioning keys. As an example, with both heading and pitch tracking turned on a continuous press of the right arrow key will cause the camera to orbit the aircraft since the camera heading is constantly updated to point to the aircraft center on each movement.

You may want to disable the Tracking options while you are positioning the camera to new base coordinates.

- The coordinate system between the 3D cockpit view and the Free (External) camera view of X-Plane is not in perfect alignment. Transitioning between External and Internal (3D Cockpit) cameras will likely result in some odd behavior.
- If you do create some cool videos please let people know you used X-Camera to create the panning affects.

## External Cameras

External cameras operate using X-Plane's free camera view. Although you can place a 3D cockpit camera outside the plane some payware aircraft may not render the plane's exterior properly when in 3D cockpit mode. You may also notice that sounds are not rendered properly if you use a 3D cockpit camera as an external view camera.

<https://www.youtube.com/watch?v=B02dbKir2oo&t=1m19s>

Tutorial Link 11

Marking a camera as an external camera will instruct X-Camera to operate in the X-Plane Free Camera view mode. With X-Plane 9 no other views will be available if you have an X-Camera external camera selected. With X-Plane 10 and above only the X-Plane Free Camera view will be unavailable. Other X-Plane views such as chase, etc. should still work although without the X-Camera features.

Using transitions between a 3D cockpit camera and an external camera will likely exhibit some strange behavior. We recommend setting up categories with either all 3D cockpit cameras or all external cameras if you want to use transition effects between cameras in the same category.



## External Camera

A basic external camera is still attached to the plane. As the plane moves the camera will move with it and the camera's heading, pitch, and roll relative to the scenery will adjust in sync with the plane. Pitch and roll can be forced to a level state by selecting Level Camera.

## Scenic Flyer Panels

X-Camera supports an optional integration to the Scenic Flyer plugin, see the section on optional integrations. If you have the Scenic Flyer plugin installed you can use the GA Panel and Glass panel camera options to show the Scenic Flyer panels when that camera is selected. See the following figure for an example.




Figure 8

<https://www.youtube.com/watch?v=SAP-ySvCtIc&t=5m07s>

Tutorial Link 12

## Cineflex Camera

A Cineflex camera is an external camera where the camera heading, pitch, and roll are independent of the plane but the X, Y, and Z coordinates of the camera continue to move with the plane. This camera is attempting to simulate the gyro-stabilized Cineflex Camera system which is popular on helicopters.

This is a relatively new idea for X-Camera so please don't hesitate to give us feedback and suggestions for improving the Cineflex camera.

## Free Camera

The free camera is basically a world camera. As soon as you mark a camera as a free camera the camera will be anchored to the plane's current location in the world and will no longer be attached to the plane. You can force a free camera to automatically adjust its heading and pitch to track the plane by using the Track Heading and Track pitch options.

Although you can define free cameras associated with an aircraft it makes much more sense to use them with Airport camera definitions. See the section on Airport Cameras for further detail.

## Target Following Camera

A target following camera will track a predefined target defined by a latitude, longitude, and elevation in meters. Targets and target following cameras are explained in detail in the targets section of this manual.

## X-Plane 9 Chase Camera

This type of camera attempts to replicate the X-Plane 9 chase view which is sometimes preferred by users over the X-Plane 10 chase view. With this option enabled X-Camera will place a camera directly behind the plane. You can adjust the distance behind the plane but you cannot move the camera left, right, up, down, or adjust its pitch and heading.

X-Camera will keep the camera level during flight but it will adjust the pitch of the camera to match the plane's pitch. This will come close to replicating the behavior of the X-Plane 9 chase view on X-Plane 10.

<https://www.youtube.com/watch?v=SAP-ySvCtIc&t=17m46s>

Tutorial Link 13

## AI Perspective

By default the orientation of any external "non-free" camera is oriented relative to the user's aircraft. X-Camera has the ability to change that orientation to any of the configured X-Plane AI aircraft. As an example, if you have a tail camera setup on your plane and you have AI planes configured in X-Plane you can toggle the orientation to an AI perspective and your camera will now give you a tail view of the currently selected AI plane.

You can toggle AI perspective on or off from the Mini Control panel. You can also select the next or previous AI plane from the Mini Control panel.

Note: You must have some AI planes configured and you must have an external camera selected. AI orientation does not work with internal cockpit cameras.

There are also five commands you can map to keys or joystick buttons that will toggle AI orientations and allow you to select AI aircraft.

1. "SRS/X-Camera/Toggle\_AI\_Perspective"
2. "SRS/X-Camera/Select\_Next\_AI\_Plane"
3. "SRS/X-Camera/Select\_Previous\_AI\_Plane"

4. "SRS/X-Camera/AI\_Scale\_Up"
5. "SRS/X-Camera/AI\_Scale\_Down"

When you have a free camera, such as an airport camera, and you have pitch and heading tracking on the camera will track the currently selected AI plane when AI perspective is enabled.

There are some limitations to AI perspective:

- X-Camera is not currently aware of the size difference between your plane and the AI aircraft. A tail view on a Cessana 172 that is only ten meters away from plane's center of gravity is going to be to be in the middle of a 747's fuselage when you select AI perspective.

There is a potential for X-Camera to be smarter about this in the future so that it can either up-scale and down-scale the cameras based on the difference between the users aircraft size and the selected AI plane. In the mean time scale up and scale down buttons will appear in the mini control panel when AI Perspective is enabled.

These buttons will add a scaling modifier to the camera coordinates to move it in or out allowing you to adjust for the difference in plane size. The scaling is temporary and does not affect the camera definitions in your camera file.

- AI Aircraft can roam a fair distance from your user's aircraft. Your scenery may not render to the same fidelity when you have an AI perspective selected.
- Do not expect to hear the sounds from an AI plane. As a matter of fact, some user aircraft sound systems are not that sophisticated and they may not be aware of the fact that your camera is many miles away from the user's plane when AI perspective is selected. It is not uncommon to hear the sounds of your Baron 58 even when you have an AI perspective on a heavy metal 747.

<https://www.youtube.com/watch?v=SAP-ySvCtIc&t=17m46s>

Tutorial Link 14

## Airport Cameras

### Overview

Airport cameras have all the same features as aircraft cameras but they are associated with an airport icao code rather than an aircraft model. Free cameras are the most logical camera type to use as airport cameras as they are fixed to a location at an airport or nearby terrain and do not move with the aircraft.

If you toggle to an airport camera view, X-Camera will locate the airport camera file that is the closest to the plane's current position within a 20 nautical mile radius. If no airport camera files can be found within 20 nautical miles, X-Camera will keep the view associated with the aircraft.

<https://www.youtube.com/watch?v=B02dbKir2oo&t=9m07s>

Tutorial Link 15

## Airport Camera File Types and Names

There are two types of airport camera files, My Airport Cameras and Community Airport Cameras. The file layout and naming convention are identical for both types of files, the only difference is where they are stored and the how they are selected.

My Airport Cameras are stored in:

X-Plane/Resources/plugins/X-Camera/MyAirportCameras

Community Airport Cameras are stored in:

X-Plane/Resources/plugins/X-Camera/ CommunityAirportCameras

Airport camera files are named by the ICAO code of the airport they represent. As an example KSFO.csv is the airport camera file for San Francisco International. The name of the file is critical as this is the way X-Camera finds the nearest airport camera file. If X-Camera finds a matching file in both the MyAirportCameras directory and also in the CommunityAirportCameras directory, the file in the MyAirportCameras directory takes precedence.

Sometimes you will have airports in extremely close proximity to each other and it might make sense to combine them into one file. A very good example of this is KSFO. At that airport there is a helipad, SFO1 and an FBO pad SFO2. You could define three separate airport files for each of these but the challenge is your plane may really be interested in a KSFO camera that is physically nearer SFO1. X-Camera might load the wrong camera file. The way to overcome this is to rename KSFO.csv to KSFO-SFO1-SFO2.csv. X-Camera will look for the four character icao code anywhere in the file name. If it finds it, it will use that file.

Camera files are simple comma separated text files. You can use a plain text editor, Microsoft Excel, or Google Sheets to edit these files. You would use of these editors to manually combine airport files. Make sure you do not have more than 10 unique category names and no more than 100 camera lines for each category.

Note: You do not want to combine airports that are more than a few miles from each other. X-Plane's coordinate system has variable reference points based on the loaded scenery. The physical location of a camera will not be at the exact same place with different scenery tiles loaded. In other words you can't place a free camera in New York into a San Francisco airport file and expect it to render properly when the plane is in San Francisco.

## Creating Airport Cameras

X-Camera does not currently ship with Airport cameras defined. However, you can use X-Camera to automatically populate airport cameras from the scenery for that airport. You can enhance the generated files by adjusting camera placement and options and you can add additional viewpoints.

<https://www.youtube.com/watch?v=B02dbKir2oo&t=9m04s>

Tutorial Link 16

This is accomplished by locating the aircraft at the airport you want to define cameras for and then place the plane as close to the desired camera location at that airport. Open the control panel and check the Airport Cameras checkbox located in the upper right corner of the control panel.

X-Camera will locate and open an existing airport camera file if one can be found for that airport and if it can't find one it will create a new one in the MyAirportCameras directory. If it does create a new one a single category with a single free camera will automatically be created at the current aircraft's location.

You can add additional cameras and position them with keyboard keys or you can move the plane to another camera location and add one there. Note, when you add a camera, X-Camera clones the current camera, which means the new camera will be at the cloned camera's location. If you want this camera to be where the plane is currently located simply uncheck and recheck the free camera checkbox. This forces the new free camera to the same location as the plane.

The Track Camera Heading and Track Camera Pitch options are particularly useful for airport cameras as it instructs the camera to track the plane's location. As an example, a free camera with these options set will adjust its heading and pitch to always point at the aircraft, such as during take-off, landing, taxi, and push back from a gate.

## Generating Airport Cameras

Airport cameras can be generated from the scenery files of the nearest airport. When you have selected an Airport Camera file a "Generate Airport Cameras" button will appear toward the top right of the control panel, see Figure 9.




Figure 9

Clicking the "Generate Airport Cameras" button will cause a new dialog to appear that allows you to adjust camera generation options, see Figure 10



Figure 10

## Horizontal and Vertical Offsets

You can specify a horizontal and vertical offset from the scenery's specified latitude and longitude of the runway or starting location. This is used so the camera is not right on top of those locations.

Sign cameras are placed directly over the sign so you can't specify a horizontal offset but you can specify how high the camera will be off the ground.

## Sign Camera Culling Radius

Depending on your scenery there can be numerous taxiway signs, many of them in very close proximity to each other. You can specify how far away each sign camera needs to be from an adjacent sign camera. If a sign camera is within the specified radius of an already added sign camera then it will not be added to the category.

## Forward Facing Starting Position Camera

The default placement of starting locations cameras is to put them in front of the aircraft starting position by the specified horizontal and vertical offset. If you check this option the camera will be placed behind the aircraft at the starting location.

## Create Airport Targets

Targets are locations defined by latitude, longitude, and elevation in meters. X-Camera can create targets for airport runways, viewpoints (like towers), and helipads. Enable this option to create targets for this airport. Refer to the targets section of this manual for greater detail on targets and target following cameras.

## Airport Camera Creation Notes

When you generate airport cameras any existing camera definitions in the currently loaded airport camera file will be deleted. If you save the camera file or switch to an aircraft camera which will cause

the airport camera file to be saved, you will lose any previously defined airport cameras that were in the file prior to generating cameras. It is a good idea to make a copy of any airport camera file that you put a bunch of time into creating specific cameras prior to running the generation option on that file.

The cameras generated are very dependent on the airport detail defined in the corresponding scenery file. If you are at an airport with only the default scenery available then it is highly likely you won't get any sign cameras and you may be limited to just runways.

Generated cameras will have the track heading and pitch option set by default. This allows the airport camera to always track the position of the plane. You can disable this if you want a camera to have a static heading and pitch.

Cameras created for a specific scenery set may not be placed properly on a different scenery set. Say as an example you created airport cameras for an airport but then you upgraded that airport to a more advanced scenery set. The previously defined cameras may not be in the proper locations.

If you choose to share your camera files make sure you note the scenery name, author, and version if available.

## Joining Airports

On occasion there are a number of airports in very close proximity to each other. A very good example of this is the heliport and FBO pad at KSFO. It makes sense to combine these into one airport camera file. The way this is done is to create the KSFO.csv using the instructions in the previous paragraphs. Exit X-Plane and go to the X-Plane/Resources/plugins/X-Camera/MyAirportCameras directory and rename KSFO.csv to KSFO-SFO1-SFO2.csv.

After restarting X-Plane and editing airport cameras while at KSFO you will notice that the newly renamed file is the one actually being used. The same thing will happen if you place your plane at the KSFO heliport or FBO pad.

## Selecting Airport Cameras

Whenever you are in an aircraft view and you attempt to select an airport camera, X-Camera will first try to find the nearest airport camera file that is within 20 nautical miles of your plane. If X-Camera cannot find a matching file it will not change the view. If the same thing is done while the Control Panel is open, X-Camera will create a new airport camera file for the nearest airport found in the X-Plane navigation database.

There are five X-Camera commands that can be mapped to joystick buttons or keys to select airport cameras. See Figure 12.

- Toggle Airport Cameras
  - This command will toggle back and forth between the last aircraft camera and the last selected airport camera. If you are currently on an aircraft camera view and no airport camera file can be located for the nearest airport, then the view will not change and will stay in the current aircraft camera.

- Toggle Nearest Airport Camera
  - This command is very similar to Toggle Airport Cameras with the difference being that X-Camera will locate and select the camera nearest to the aircraft if an airport camera is being toggled in.
- Select Nearest Airport Camera
  - This command will load the nearest airport camera file if it is not the current active camera file and then it will select the nearest camera to the aircraft. Subsequent operations of this command will continue to find and select the nearest camera.
- Auto Select Nearest Airport Camera
  - This command will load the nearest airport camera file if it is not the current active camera file and then it will select the nearest camera to the aircraft. While you stay in the airport camera view X-Camera will continuously evaluate which airport camera is closest to your plane as it moves. As soon as X-Camera detects a closer camera it will automatically select it.
- Toggle Auto Nearest Airport Camera
  - Similar to Auto Select Nearest Airport Camera but the command will toggle back to the aircraft file if the airport file is currently selected.

## Airport Cameras with an Unregistered Version of X-Camera

Airport cameras are a registered feature of X-Camera. If you are running an unregistered version of X-Camera no airport camera files will be available. However, you can try out the feature. X-Camera will allow you to define airport camera files that will work for the current active session of X-Plane.

Experiment with them at your favorite airport. The airport files will be properly formatted and saved to the X-Camera/UnRegisteredAirportCameras directory. You can copy them to the MyAirportCameras directory and use them once you are registered.

The airport camera generation feature works in the unregistered version of X-Camera but it will create a limited set of runway, starting location, and sign cameras. Hopefully enough so that you can get a sense of how the feature works.

Note: If you shut down X-Plane and restart it any airport cameras defined for a given airport will overwrite the same file in the UnRegisteredAirportCameras directory. We don't recommend spending a lot of time defining a lot of cameras using an unregistered version of X-Camera. It is all too easy to forget the above behavior and accidentally delete all your hard work.

## Targets and Target Following Cameras

Targets are locations defined by a latitude, longitude, and elevation in meters. Target following cameras are a special type of external camera that is attached to your plane and it has the ability to track a selected target.

<https://www.youtube.com/watch?v=SAP-ySvCtIc&t=6m46s>

Tutorial Link 17



## Creating Targets

Targets can be created a number of ways depending on the type of camera that is currently selected and by using the X-Camera menu command “Save Target Position”.

1. Targets can be created by simply flying your plane, helicopter, or VTOL to a location in space. Use the X-Camera menu command to “Save Target Position”. A dialog box will open allowing you to name the target and save it.
2. Use your plane, helicopter, or VTOL to get close to the target location. Using the X-Camera control panel create a temporary free camera. Use your arrow keys or mouse move keys to position the free camera exactly where you want it in the scenery. Use the X-Camera menu command to “Save Target Position”.
  - a. **Note:** when saving a target from a free camera the free camera’s location is saved as the target, not the plane’s location and elevation.
  - b. **Note:** You will probably want to restore your plane cameras or delete the free camera from your aircraft once you have saved the target.
3. Select a target following camera and then select the free target. Use the middle mouse button, or simulated middle mouse button on a MAC or Linux system, to position the free target at the red X on the middle of the screen. This will adjust the free target’s location. Use the X-Camera menu command to “Save Target Position”. This will save the free target’s location as a permanent named target.
4. Edit the comma delimited file in X-Plane/Resources/Plugins/X-Camera/My Targets/MyTargets.csv and manually add a target by specifying the target name, date of creation, latitude, longitude, and elevation in meters.

## Target Following Cameras

Target following cameras are an option on an external aircraft camera that will track a selected target. You can choose this option on a camera using the control panel.

When a target following camera is selected X-Camera will find all the targets within a 30 nautical mile radius. Targets can be selected using the target commands outlined in the next section. Once a target is selected the camera will track the target as the aircraft moves.

X-Camera will evaluate the new set of targets as soon as the plane moves more than 15 nautical miles from the last location targets were collected. This will happen automatically but you can also force new targets to be collected using the command: “SRS/X-Camera/Select\_Nearest\_Target”.

## Free Target

A free target is a temporary target that is created each time X-Camera collects targets. The free target is initially set to a location ahead of the aircraft. The distance to the free target is determined by the aircraft’s altitude above ground, it’s heading, and an initial target camera pitch of -10 degrees.

You can reposition the target by using the middle mouse button, or simulated middle mouse button on a MAC or Linux system. When a target camera is selected a red X will appear in the center of the screen. While continuing to activate the middle mouse button move the mouse to position the red X to where you want the target.

It can be difficult to aim a free target using mouse look while the sim is operating and the plane is moving. There is an option in the settings menu that will optionally pause the simulation when you are aiming a free target. The pause will be toggled as soon as you release the middle mouse button.

#### Free Targets Note:

- The camera must be pitched with the mouse to an angle less than zero so that it intersects with a location on level ground. It is generally easier to position a free target if the plane is up in the air.
- X-Camera calculates the free targets position by calculating the point on the ground that the camera is aimed at. This is not going to be an extremely precise way of creating a target but it is a fast way to track a ground location without having to create a permanent target.
- Free targets will be reinitialized as soon as it is detected that they are more than 30 nautical miles away from the plane.
- The target aiming functionality looks for a hard or water surface under the aiming point and then attempts to place the target one meter above the surface. You can place targets on roof tops assuming the scenery defines the roof as have a hard surface. You can also place targets on objects like aircraft carriers but if the carrier is moving the target does not follow the moving aircraft carrier. It might be a cool feature to add in the future if I can figure out how to make that work.

## Target Commands

There are a number of commands associated with targets that can be mapped to joystick buttons or keys:

Command	Description
SRS/X-Camera/Select_Nearest_Target	Collects targets within a 30 nautical mile radius and selects the one nearest the plane
SRS/X-Camera/Select_Next_Target	Selects the next target in the collection. It will wrap to the first target when at the end of the list
SRS/X-Camera/Select_Previous_Target	Selects the previous target in the collection. It will wrap to the last target when it is at the beginning of the list
SRS/X-Camera/Toggle_Target_Information	Turn the target display information at the

	bottom of the screen on or off.
<b>SRS/X-Camera/Toggle_Target_Reciprocal</b>	Switches the view on a target following camera to either be looking at the target or from the target to the plane.
<b>SRS/X-Camera/Save_Camera_As_Target</b>	Saves the current camera location as a named target. Note: the behavior of this command varies with the type of camera. See the section “Creating Targets”
<b>SRS/X-Camera/Toggle_Target_Following_Camera</b>	Toggles target following on or off for the selected camera
<b>SRS/X-Camera/Select_Free_Target</b>	Selects the Free Target from the target collection

Any of the target selection commands, nearest target, free target, next / previous target etc. will cause X-Camera to search for and select the first target following camera if the current camera is not a target following camera. The search always starts from the first category and then sequentially through each camera in the category. Your primary target following camera should be ahead of any additional target following cameras.

## Notes on Targets and Target Following Cameras

The further the target is away from the plane the less detail will be rendered when you select the target reciprocal view. This is because X-Plane limits scenery detail the further away the scenery is from the plane. This helps keep frame rates high and it is also the reason why targets are limited to a 30 nautical mile radius.

Targets are automatically recollected whenever the plane moves more than 15 nautical miles from the last location that targets were collected.

## Mini Control Panel

There is an optional mini-control panel that can be activated by mapping a key or joystick button to the command:

SRS/X-Camera/Toggle\_Mini\_Control\_Panel

When activated a control panel will appear at the bottom of the screen that will show 3 – 4 rows of buttons. The first row gives you a set of commands that are context sensitive to the type of camera you have selected. The second row allows you to select a camera category. The third row allows you to select cameras in the current category.

There is an optional forth row of buttons that will allow you to select any cameras that have View IDs assigned to them.

You can also set the mini control panel to open automatically the first time X-Camera is started. That option can be set in the settings menu as well as choosing if you want the mini control panel to have a solid or translucent background.



Figure 11

The min-control panel can also be activated by placing your mouse in the bottom 5 pixels of the screen or X-Plane window. The min-control panel will open and will remain open as long as the mouse is in the bounds of the min-control panel window or if the panel has been pinned open using the associated checkbox in the upper left corner of the mini control panel. The auto show mini-control panel feature can be disabled in the Settings dialog.

The mini-control panel has limited screen real estate. If you use long category names it is likely that not all the categories will fit on the panel. The same is true for cameras. Since a category can have up to 100 cameras the mini control panel will only be able to display the first few camera names that fit on the screen. Keep this limitation in mind as you create and name your categories and cameras. Joystick Button Assignments for more information

<https://www.youtube.com/watch?v=B02dbKir2oo&t=3m14s>

Enhancements to mini-control panel in version 2.2:

<https://youtu.be/vctMkivRaoo?t=67>

Tutorial Link 18

## Joystick Button Assignments

There are a number of X-Camera commands that can be associated with Joystick buttons or keyboard commands. See Figure 12 for the partial list. Note the red box around the custom cmnds from plugins selector. After selecting a button you will need to use this selector to find the SRS/X-Camera commands by traversing the command tree. SRS stands for Stick and Rudder Studios and distinguishes our plugins from other authors.




Figure 12

Most of the control mappings are pretty self-explanatory. The PAN options are typically mapped to an eight-way hat switch. Although you can map all hat switch commands to X-Camera we recommend mapping the 90° commands to X-Plane's panning commands and map the 45° commands to X-Camera's commands such as "Pan\_Left\_And\_Up".

The exact same convention is used to map keyboard keys in X-Plane to the above X-Camera commands.

Assigning buttons to custom plugin commands is often a confusing topic for new X-Plane users. Here is a link to a few YouTube videos that demonstrates how you make these assignments.

This is a direct link to the part of one of the X-Camera tutorial videos that shows you how to map commands to X-Camera:

<https://www.youtube.com/watch?v=B02dbKir2oo&t=20m57s>

Tutorial Link 19

The video is not for specifically for X-Camera but it covers the topic generically using Scenic Flyer as an example.

<https://www.youtube.com/watch?v=LvFZXzq6gQ0>

## Sharing Camera Files

Camera files are simple CSV text files that can be shared easily right from the main control panel. There is a detailed explanation of the Community Files earlier in this manual.

## Sharing Guidelines

Here are a few guidelines for sharing your camera files:

- We recommend using a default 70 degree field of view in your rendering options when you create your camera definitions. This is not a hard and fast rule but the more variation there is in the field of view the more adjustments will need to be made when users download your camera file.
- Make sure the pilot view camera is always the first camera in the first category. This will ensure that the “Auto Correct” on load will be able to do the best job adjusting the cockpit cameras.
- Place cameras that generally go together in the same category. Cockpit, Cabin, External Flight, Animations, are examples of some common organizations. The reason for this is so that you can use Next and Previous command assignments to navigate easily between cameras of a similar nature, such as sequencing through all cockpit cameras.
- Be creative. Some of the coolest features of X-Camera are the very unique animated camera sequences you can do with transitions. If you come up with something cool, create a YouTube video and share it on X-Plane.org and let people know you used X-Camera to create it.

## Settings

X-Camera has a few settings that are global, not specific to a camera or a plane's set of cameras. These settings can be adjusted by accessing the settings menu item. Figure 13 illustrates the setting UI.




Figure 13

## Pan and Movement Speeds

Pan speeds are in degrees. You can specify pan speeds for the four movement ranges, Small, Medium, Large, and Very Large.

Movement speed is in meters. Similar to the pan speeds you can specify the distance over the four movement ranges, Small, Medium, Large, and Very Large.

If you plan to use the mouse move feature you will likely want to adjust the movement ranges to suit your screen resolution and mouse sensitivity. Generally the ranges are used for the following:

- Small – most appropriate for walk-mode or very close-up camera positioning
- Medium – most suited for placing cameras in the cockpit
- Large – most suited for placing external cameras that are relatively close to the plane
- Very Large – most suited to placing free cameras around an airport or scenery

The Pan and Movement Speed Factors determine the multiplier or divisor for the fast and slow movement commands. X-Plane 9 supports Normal and Fast movement commands while X-Plane 10 supports Slow, Normal, and Fast movement commands. Slow commands will divide the speed range value by the factor and fast commands will multiply the speed range value by the factor. Normal speed commands use the pan and movement speeds directly with no modification.

Using the settings in Figure 13 let's assume your range is currently set to Medium. You are using X-Plane 10 so it is possible to have Slow, Normal, and Fast panning commands. A slow command would result in a .333 degree movement ( $1 / \text{Pan Speed Factor } 3$ ). A normal pan command would result in a 1 degree movement, and a fast pan command would result in a 3 degree movement ( $1 * \text{Pan Speed Factor } 3$ ).

As you change the range with the <CTRL> + and – keys the range will change as will the calculations above.

Enable Pan Speed Toggle allows you to map a joy stick button to increment the pan speed from slow to normal, and to fast. This is useful if you have one hat switch that is mapped to either the slow, normal, or fast X-Plane panning commands. When you toggle the pan speed, X-Camera will pan at the current pan speed regardless of which X-Plane pan speed command is mapped to the hat switch.

If Enable Pan Speed Toggle is disabled X-Camera will pan at the speed indicated by the mapped X-Plane command.

Remember to Save Settings when you are done making changes.

## **Auto Show Mini-Control Panel**

The mini-control panel can be set to auto open if the mouse is placed in the lower 5 pixels of the screen or X-Plane window. Uncheck this option to disable that feature.

## **Open Mini-Control Panel on Start**

You can set the mini-control panel to open the first time X-Camera is started. After that you can use a mapped command to toggle it open and closed. If this is used in conjunction with the Auto Show Mini-control panel the panel will be opened and initially pinned open. You can use the checkbox in the upper left corner of the Mini-control panel to unpin the panel if needed.

## **Enable Transparent Mini Control Panel**

Prior to X-Camera 2.2 the mini control panel could only be displayed with a solid background. With this option enabled the mini control panel will be rendered with a translucent background similar to the main control panel.

## **Enable Solid Control Panel**

This option will present the control panel with a solid background. The default setting is a translucent control panel background.

## **Hide Favorites in Mini Control Panel**

By default X-Camera will create a fourth row of buttons in the mini control panel any time you have cameras with view IDs assigned to them. This allows you to select any of your favorite cameras using the buttons in this fourth row. Turning this option on will suppress the creation of this fourth row regardless of view ID assignments.



## Show Target Information

When a target following camera is selected information about the target such as target name, bearing, and distance will be displayed at the bottom of this screen. Refer to the target section of this manual for more details on targets and target following cameras.

## Pause When Aiming Target

It can be difficult to aim a free target using mouse look while the sim is operating and the plane is moving. This will optionally pause the simulation when you are aiming a free target. The pause will be toggled as soon as you release the middle mouse button.

## Lock Keyboard Control

Due to some recent changes in X-Plane a conflict arose around the X-Plane `general_up` and `general_down` commands with regard to using these to respond to ATC. X-Camera has these commands mapped to camera move up and down and was intercepting the commands when the ATC window was open. Setting this option allows you to lock out keyboard control for camera movement when the X-Camera control panel is not open. When this option is set you will not be able to move the camera with the keyboard if the control panel is not open but the commands will go to the ATC window restoring the ATC response functionality.

## Mouse Smoothing

Mouse Smoothing Factor determines how many mouse coordinates are averaged to smooth mouse look and mouse move operations.

## Head Track Smoothing

You can apply a head track smoothing factor to TrackIR camera inputs. A value between 4 and 10 may reduce the visual effects of stuttering when panning your head rapidly with a head tracking device. Smoothing factors high then 10 will start to add lag to head tracking that may not be acceptable.

## View Axis Smoothing

A view axis smoothing factor between 4 and 10 will help to smooth camera movement when using a joystick for camera movement.

## Enable Force FOV

If you enable this dialog you will see additional controls displayed on the control panel. With these controls you can enable each camera to have a specific horizontal field of view (FOV). This is accomplished using the FOV slider on the left hand side of the control panel and the FOV enable checkbox. When the checkbox is enabled you can set the FOV from 15° to 170° for each camera using the slider and the slider arrow buttons. When the FOV checkbox is disabled the camera will use the FOV setting in X-Plane's rendering options at the time X-Camera was enabled.

If you have this setting enabled you will not be able to change your horizontal field of view in the X-Plane rendering options while X-Camera is enabled. Disable X-Camera using the X-Camera plugin menu option to adjust your default X-Plane horizontal field of view. You also can not reliably run an X-Plane 11 Multi-Monitor configuration as each monitor may require a different FOV.

## Camera Smoothing Window

If you use the camera option “Smooth Camera Joins” this setting parameter can have impact on how many frames are involved in the smoothing. The default is 60 frames meaning that X-Camera will start smoothing using a three point Bezier curve 30 frames ahead of and past the camera join points.

The smooth window must be larger than 60. Note that increasing this value assumes that you have a sufficient number of frames in your camera transitions to allow for the window.

## Getting Support

This is an X-Camera FAQ available here: <https://www.stickandrudderstudios.com/x-camera-faq/>

Stick and Rudder Studios has a Q&A forum on our website where you can find answers to questions submitted by other users or where you can ask your own questions. The Q&A area can be reached by going to: [https://www.stickandrudderstudios.com/answers/?question\\_type=all&search=](https://www.stickandrudderstudios.com/answers/?question_type=all&search=)

You will need to create an account to ask or answer any questions but you can certainly review other questions and answers without logging in to the site.

## Tutorials

This manual contains links to the various YouTube tutorial videos that cover a particular topic. The full list of all the tutorials can be found here:

<https://www.stickandrudderstudios.com/x-camera-tutorial-videos/>

## New Releases and Beta Releases

If you want to be notified of new versions of X-Camera and beta testing programs you can join our newsletter mailing list here:

<https://www.stickandrudderstudios.com/mailling-list/>

Make sure you select the appropriate “Send me information about” check boxes.

## Appendix

### External Integrations

#### Head Tracking

X-Camera has a set of datarefs which can be manipulated by 3<sup>rd</sup> party head tracking solutions to provide head movement offsets to any X-Camera camera that has the TrackIR option enabled. Note that X-Camera natively supports TrackIR and any head tracking solution that can emulate the TrackIR software interface. These datarefs are useful for those products that do not emulate TrackIR.

The following datarefs are defined by the X-Camera plugin:

Dataref	Type	Comments
SRS/X-Camera/integration/headtracking_present	Int	Set to 1 to indicate that a 3 <sup>rd</sup> party tracker is going to provide head tracking input
SRS/X-Camera/integration/headtracking_x_offset	Float	X axis offset in meters. + is to the right
SRS/X-Camera/integration/headtracking_y_offset	Float	Y axis offset in meters. + is up
SRS/X-Camera/integration/headtracking_z_offset	Float	Z axis offset in meters. + is back
SRS/X-Camera/integration/headtracking_pitch_offset	Float	Pitch offset in degrees. + is pitch up
SRS/X-Camera/integration/headtracking_heading_offset	Float	Heading offset in degrees
SRS/X-Camera/integration/headtracking_roll_offset	Float	Roll offset in degrees. + is roll to the right

It is important that only one 3<sup>rd</sup> party plugin use these datarefs at one time. If headtracking\_present has a non-zero value in it when you try to attach it would be wise to report a conflict error. You should always clear the headtracking\_present dataref when you no longer will be providing input.

**Note:**

- The TrackIR camera option must be enabled on any camera that you want these inputs applied to on each frame.
- These values are offsets that will be added to the camera position on each frame. They are not absolute camera coordinates.

## Previous Change Logs

Version	Changes
2.3	<ul style="list-style-type: none"><li>• Fixed a bug where the selected camera in a category was always being forced to the first camera rather than the last one selected when using the commands SRS/X-Camera/Select_Category_1 through SRS/X-Camera/Select_Category_20</li><li>• Fixed a bug where the number of favorites was not updating when you save a view with Quick Look Emulation</li><li>• Added a setting to disable Quick Look Emulation</li><li>• Changed to code in X-Plane command handler to always evaluate a Quick Look recall if not disabled</li><li>• Added AI Perspective scale up and down</li><li>• Added X-Plane Quick Look import when creating a new plane camera file</li><li>• Added support for X-Camera to respond to saving or selecting quick look commands</li><li>• Added datarefs to support new 3<sup>rd</sup> party head tracking solutions. The first if these is SimHat</li><li>• Added support for a semi-continuous orbit</li><li>• Added support for Multi-Monitor roll dataref in X-Plane 11.02</li><li>• Added settings button to mini control panel</li><li>• Adjusted for camera pitch when positioning cameras with the keyboard</li><li>• Improved camera positioning when heading and pitch tracking are turned on</li><li>• Fixed bug that allowed control panel title bar to get stuck under X-Plane menu</li><li>• Changed control panel menu item to be a toggle control panel function</li><li>• Added an option for a solid background on the control panel</li><li>• Added an option to hide favorite view ID cameras from the mini control panel</li><li>• Improved yoke hiding functionality</li><li>• Added datarefs for XPRealistic integration</li><li>• Added support to move cameras using a spare joystick controller</li><li>• Added AI Aircraft orientation</li><li>• Fixed problem with TrackIR offset translations for rear facing cameras</li><li>• Added camera property to hide the yoke</li></ul>
2.2.1	<ul style="list-style-type: none"><li>• Fixed a problem where it was not possible to share aircraft files with the community on OSX systems</li></ul>
2.2	<ul style="list-style-type: none"><li>• Fixed the problem that prevented X-Plane views from being activated</li><li>• Changed the method for smooth camera joins to use a three control point Bezier curve algorithm</li><li>• Improved the “Nearest Airport Camera” to find the closest airport camera file within a 20 nautical mile radius of the plane.</li><li>• Adapted the X-Plane 11 Multi-Monitor support on external cameras to work with the new way X-Plane 11 PB6 supports offset rotations</li><li>• Fixed a bug in linear and smooth transitions when joining cameras with the auto advance feature. The bug introduced an additional frame at the camera join points which would look like a micro-stutter as the transitions were processed</li><li>• Modified the “Create Orbit” function to not use “Smooth Camera joins”. This is no</li></ul>

longer needed with the aforementioned transition bug fixed

- Add transitions for X, Y, and Z CG offsets
- Added a SMOOTH\_WINDOW parameter to the X-Camera.ini file so that the default 60 frame smooth window for the smooth camera joins option can be adjusted
- Removed HotKey for toggle walk mode as it conflicted with movie recording
- Added X CG Offset
- Fixed problems with applying Y and Z offsets
- Added Next View ID and Previous View ID select commands
- Added Select Category by ID command
- Added Cinema Verite option per camera
- Added Copy and Paste Camera
- Added Copy and Paste Camera Set
- Implemented FOV for Bezier curve transitions
- Added "Toggle Target Following" to the list of common camera commands on the Mini Control Panel
- Fixed some focus problems on a few dialogs that was caused by the opening and closing of the Mini Control Panel
- Fixed a bug with enable temporary positioning where the camera would not get restored if it was the current camera and then it is selected again via a view\_id command or by the Mini Control Panel
- Fixed a problem where Pan Speed Toggle could initialize in a random state if settings were never saved
- Significantly enhanced the Mini-Control Panel
  - Add a row for cameras with View ID's assigned
  - Add a row of context sensitive commands based on current camera
  - Allowed Mini-Control Panel to be pinned
  - Added more context to the Mini-Control Panel title bar
- Significantly enhanced the Community Aircraft File functionality
  - You can submit your camera files to the community from directly in X-Camera
  - You can update your submissions with new versions directly from within X-Camera
  - You can refresh your cache from the community file server directly from within X-Camera
  - You can filter the browse list for matches on aircraft type or author, no need to hunt and peck through the list
  - The list is now sorted by aircraft type
  - When you load a file from a plane that is not exactly the same but similar, X-Camera will optionally attempt to fix all the cockpit cameras

## 2.0

- Fixed a bug where X-Camera was auto-enabling on an aircraft with no camera file when a View ID command was executed.
- Fixed a bug where the camera was not always properly restored when X-Camera was disabled
- Added support for zoom transitions for external cameras
- Added HeadShake Toggle Command

- Added System Check Menu Item to test for compatibility with other plugins
- Added Mini Control Panel
- Added a hidden camera option for use with multi-camera animations
- Added ability to browse and import community aircraft files
- Added Author and Version data to aircraft camera files
- Added a mouse move capability
- Added an ability to adjust the mouse smoothing for mouse look and move
- Added a fourth movement range, Very Large
- Added Orbit and Fly-By animation generators
- Added Walk Mode Toggle Command
- Increased categories to 20 from 10
- Added an ability to specify transitions in seconds. The required transition frame count will be calculated on the fly based on your current frame rate.
- Added an ability to generate airport cameras from scenery files
- Added support for Airport Cameras
- Added a walk mode toggle command so it can be mapped to a Joystick button
- Allowed camera FOV to be set to 15 degrees as the new minimum
- Added Bezier Curve Transitions
- Added an ability to see fully linked transitions while the control panel is open
- Added the ability to insert cameras and categories before the current camera or category
- Enhanced camera settings so that a camera will remember the last range setting used to position it. This is useful for outside cameras where you might want the camera to remember the large range setting for moving the camera later.
- Added support for external cameras
- Added support for a Cineflex camera
- Added support for a free camera

## 1.1

- Fixed a problem where X-Camera would not auto enable 3D Cockpit if you changed the airport or runway.
- Fixed a bug where X-Camera was swallowing all X-Plane commands if it was enabled and not in 3D cockpit mode. This made things like the free camera not respond to movement input
- Fixed a divide by zero bug when an Axis View was assigned to a removed joystick
- Added support to enable or disable view axis input by camera
- Added Support for View Axis
- Added Tracking Camera support
- Added Level Camera Support
- Added camera join smoothing
- Revamped the transition framework
- Added support to specify a horizontal field of view between 55° and 170° for each camera
- Added support for an initial zoom factor for each camera
- Added support for X-Camera to Auto-Enable if it finds an existing camera settings file for a newly loaded aircraft.
- Added TrackIR limits
- Added support for many of the standard X-Plane view commands such as glance

	<p>left/right, look up and left/right, left/right 135, etc.</p> <ul style="list-style-type: none"> <li>• Added support for a pan speed toggle between slow and fast panning. This is particularly useful when you have one hat switch and want to change the pan speed.</li> <li>• Added support for adjusting the movement and panning ranges over three speed setting, Small, Medium, and Large. Medium is the default.</li> <li>• Removed original keyboard maps for moving and panning the camera and replaced them with X-Plane command equivalents. Read the Release Notes section for more detail. This is a significant change.</li> <li>• Removed code that could cause a crash if your X-Plane.prf file had more than 10,000 lines in it.</li> <li>• Removed registration email from X-Plane log.txt file to protect registered user's privacy if they need to send the log file to other people.</li> </ul>
<b>1.0</b>	<ul style="list-style-type: none"> <li>• Added support for LinuxTrack. Read the LinuxTrack section of this manual for more detail</li> <li>• Added support for 8 way hat switch panning</li> <li>• Added middle mouse button simulation for easier mouse look operation on Linux and Mac</li> <li>• Added enhanced transitions that allow you to create very cool effects for making flight movies. Also added license key support for these more advanced features.</li> <li>• Added command to restore a camera to its original position</li> <li>• Added roll support for TrackIR, LinuxTrack, and HeadShake. X-Camera now supports a full 6 DOF with these three options.</li> <li>• Fixed a problem where X-Camera was not able to save settings for each aircraft if there was more than one .ACF file in the aircraft directory.</li> </ul>
<b>0.5</b>	<ul style="list-style-type: none"> <li>• Walk mode will now be automatically disabled if you switch cameras</li> <li>• Added the new feature "Enable Temporary Positioning"</li> <li>• Adjust the way TrackIR worked. It should now use less CPU and should reduce some reported stutters.</li> </ul>
<b>0.4</b>	<ul style="list-style-type: none"> <li>• Port to Linux</li> <li>• Adjusted smoothing on mouse look</li> </ul>
<b>0.3</b>	<ul style="list-style-type: none"> <li>• Fixed a bug in the Mac version where the X-Camera.csv files were being saved in the X-Plane base directory rather than the specific aircraft directories.</li> </ul> <p>Note: If you used version 0.2 on a Mac and saved any of your camera settings these X-Camera.csv files will be in the X-Plane base directory. They need to be moved to the specific aircraft directory and renamed to X-Camera.csv. If you don't do this your camera definition for any aircraft will default to the one pilot view camera in the Cockpit category</p>
<b>0.2</b>	<ul style="list-style-type: none"> <li>• Ported code to Mac. X-Camera now supports Apple Macintosh platforms as well as Windows</li> <li>• Animated camera to original position after mouse look middle button release if the camera was set to smooth transition</li> </ul>
<b>0.1</b>	<ul style="list-style-type: none"> <li>• Replaced Walk Mode button on the control panel with a check box which should be more intuitive</li> <li>• Corrected behavior of Camera Home command to set the camera to the original pilots head position in the virtual cockpit</li> <li>• Fixed a problem where key assignments to X-Camera commands were not retained when X-Plane</li> </ul>

	<p>was restarted. Note: you will need to reassign any commands that were associated to keyboard keys.</p> <ul style="list-style-type: none"> <li>• Fixed a problem where smooth transition was not working when you used keyboard or joystick assignments to select views within the same category</li> <li>• Added mouse look capability using middle mouse button</li> <li>• Removed restriction of 2 categories and 3 camera views per category in the free version. The free version now supports 10 categories and 100 camera views per category</li> </ul>
<b>0.0</b>	<ul style="list-style-type: none"> <li>• Initial Release</li> </ul>

## Prior Release Notes

### 2.3

The following YouTube video demonstrates the major new features in X-Camera 2.3.

<https://www.youtube.com/watch?v=D0qj5KQZe1s>

### Import X-Plane Quick Look Views

X-Camera will now support importing X-Plane quick look views for any 3D cockpit, chase, circle, or ride-along views that have been saved as X-Plane quick look views. The import function is offered as an option when X-Camera is enabled with no previous camera file defined for that plane. This should make it easier for new X-Camera users to adapt any of their existing defined X-Plane quick looks to X-Camera.

### Responding to Quick Look Save and Select Commands

X-Camera will now respond to the X-Plane Quick Look save and select commands. These commands are typically mapped to the numpad keys 0 – 9 with the <ctrl> modifier used to save the current view as a quick look.

There is an option on the settings dialog to disable Quick Look emulation. Disabling Quick Look emulation may be desirable if you want to have your X-Plane quick look keys mapped to X-Plane specific views such as the circle view.

### New External Datarefs for 3<sup>rd</sup> Party Head Tracking

There are now seven new datarefs that can be used by 3<sup>rd</sup> party head tracking solutions to integrate with X-Camera in addition to the native integration with TrackIR and LinuxTrack. These datarefs are outlined in the appendix.

The first 3<sup>rd</sup> party solution that will take advantage of this is SimHat.

<http://www.simhat.com/>

### Continuous Orbit



You now create orbits that will orbit semi-continuously. We use the word semi-continuously as the orbit will be limited to roughly 60 rotations but you will likely get bored watching that many so the limitation is probably acceptable.

## Multi-Monitor Roll Support

X-Plane 11.02 RC1 now has a new dataref that represents the pilot's head roll. In previous version of X-Plane 11 the pilot head roll from TrackIR, HeadShake, XPRealistic, and any specified camera roll would not get applied to the side monitors in a multi-monitor configuration. X-Camera 2.3 beta 3 now takes advantage of this new dataref so roll offsets should be properly applied assuming you are running X-Plane 11.02 RC1 or higher.

## New Options

New settings options:

1. You can now specify that you want the control panel to have a solid background vs the previous default semi-transparent background
2. You can optionally hide the fourth row in the mini-control panel through the use of a hide favorite cameras option.

## Bug Fixes

Prior versions of X-Camera were not taking into consideration the camera pitch when trying to move the camera. This has been corrected so that keyboard movement will always be in the direction of the camera including its heading as well as pitch.

Prior versions of X-Camera had confusing camera movement when you tried to move cameras with track heading or track pitch turned on. This was caused by the fact that X-Camera was not updating the underlying camera's heading and pitch based upon the tracking function so camera movement was in the direction of a camera heading and pitch that did not represent the current visual orientation of the camera. Beta 3 corrects that by always updating the camera's heading and pitch with the tracking heading and pitch if enabled. A side benefit of this fix is you can achieve a manual orbit by enabling both track heading and pitch and then just use the arrow keys to rotate the camera around the aircraft.

It was possible in prior versions of X-Camera to place the title bar of the control panel under the X-Plane menu. When this happened you could no longer click in the control panel title bar to move the control panel. X-Camera now checks the last control panel position when it is opened and if the control panel is too high on the screen it will center it. We have also modified the menu item to open the control panel to be a toggle function.

## Yoke Visibility

You can now use a camera option to hide the yoke in the cockpit. This can be useful for certain close-up cameras in the cockpit where a visible yoke might get in the way.

The Yoke Visibility camera option is a tri-state control. The three states are:

1. Don't Force – In this state X-Camera will not try to adjust the yoke visibility. Yoke visibility will be controlled by using the 'y' key or through other means that may have been supported by the plane model
2. Force to 0 – This option will force the hide yoke dataref to a 0 value. Depending on the plane this could hide or show the yoke. The meaning of the yoke data ref is a bit ambiguous so we have seen different aircraft designers interpret the dataref differently.
3. Force to 1 – This option will force the hide yoke dataref to a 1 value. Depending on the plane this could hide or show the yoke. The meaning of the yoke data ref is a bit ambiguous so we have seen different aircraft designers interpret the dataref differently.

## XPRealistic Integration

We have worked with the developer of XPRealistic to develop a more in-depth integration between the products. This new integration supports the ability to turn XPRealistic camera effects on and off by camera in a similar fashion as it does for HeadShake. You will need version 1.0.6 of XPRealistic to take advantage of this improved integration.

<http://xprealistic.com/>

## Moving cameras with a spare joystick controller

X-Camera now supports camera movements along the X, Y, Z, Heading, Pitch, and Roll axis using a spare joystick controller. See ***Camera Positioning with a Spare Joystick Controller*** for further information.

## AI perspective

X-Camera now has the ability to toggle between an orientation of the user plane or various AI planes using external cameras. As an example, if you have a tail / chase view camera on your plane you can toggle between your plane and various AI aircraft. When an AI aircraft orientation is selected you will see a tail view of the selected AI aircraft at its current scenery location. See ***AI*** for further information.

## AI Perspective Scale Up and Down

You can now scale your external cameras up and down when in AI perspective mode. This allows you to move all your external cameras out or in so you can get a good view of an AI plane that is larger or smaller than the current plane you are flying.

Scale out and in buttons show up in the mini control panel when AI perspective is on and there are AI planes to display. There are also two new commands for these functions that you can map keys or buttons to.

## 2.2

## Smooth Camera Joins

The algorithm for smooth camera joins has been improved to use a three point Bezier curve at the camera join points rather than the simple averaging that was previously used. The curve is implemented over the camera smoothing window that can be specified in the settings panel.

The “Create Orbit” function was modified to remove the “Smooth Camera Joins” option. This is no longer needed after correcting an extra frame bug in linear transitions. We recommend recreating your orbits without the “Smooth Camera Joins” option if you notice that orbits created prior to X-Camera 2.2 are not operating smoothly.

Added a settings option to increase the camera join smooth window above 60 frames. If you use the option “Smooth Camera Joins” increasing this setting may give you a smoother transition between two camera join points.

## Airport Camera

The “Select Nearest Airport” camera function has been improved to find the nearest airport camera file that has been created within a 20 mile radius of the plane’s location. Prior to beta 5, X-Camera would only select a file if it just happened to be the closest to the plane as defined by the X-Plane navigation database. This often prevented you from selecting a larger airport camera file when on approach as there would be many smaller airports along your route that you did not create camera files for.

## Walk Mode HotKey

Removed the <CTRL><SPACE> HotKey for walk mode toggle as it was conflicting with X-Plane video recording commands. If you use walk mode you will need to map a key or button to the command SRS/X-Camera/Toggle\_Walk\_Mode.

## Center of Gravity Offsets

Added an X CG offset to the UI and camera file. This affects tracking cameras where you can now adjust where the aim point is for these cameras. With no offsets the camera will attempt to track the plane’s center of gravity. The offsets allow you to adjust the aim point relative to the center of gravity.

Fixed problems with applying CG offsets for camera rotations. Heading and Pitch tracking external cameras should track to the planes rough CG +/- defined offsets.

## Compatibility with X-Plane Views

Fixed a problem where you could not activate an X-Plane view, such as the circle view, without having to activate the X-Plane menu item or command twice. With this fix you should be able to seamlessly move between X-Plane views and X-Camera views.

## New Commands

Three new commands have been added that can be mapped to joystick buttons or keys. The next and previous View\_ID commands will advance to the next or previous camera that has a View\_ID assigned to it.

You can also assign buttons and keys to the commands `Select_Category_1` through `Select_Category_20`. When these commands are activated they will select the first camera in the selected category.

**Note:** If you are using X-Assign your joystick mappings per plane may need to be re-done. The reason is X-Assign seems to have a problem when new plugins add commands to their set.

## Cinema Verite Support by Camera

You can now enable Cinema Verite by camera. By default it is off so if you were using it you will need to go to your camera definitions and turn it on for each camera. This is a feature we would like some feedback on to make sure it is working to everyone's liking.

## Copy and Paste Camera and Camera Sets

New buttons on the control panel have been added that will allow you to copy the current camera and then move to a new category and camera and paste that camera over the one you currently have selected. The copied camera will be remembered between plane loads.

There is also an ability to copy the entire camera set for the current plane you have loaded. After copying the set you can load a new plane and paste the entire set. The auto correct cockpit cameras feature that is available when loading community files is also available when pasting a camera set.

## FOV Transitions

FOV transitions have been available for smooth and linear transitions since X-Camera 2.1 but they were never implemented for Bezier curve transitions. This is now available in 2.2.

## Community File Support

X-Camera 2.2 has significant improvements to the support for submitting and browsing user community submitted aircraft definition files. Here are some of the highlights of the improvements:

- You can submit your camera files to the community from directly in X-Camera
- You can update your submissions with new versions directly from within X-Camera
- You can refresh your cache from the community file server directly from within X-Camera
- You can filter the browse list for matches on aircraft type or author, no need to hunt and peck through the list
- The list is now sorted by aircraft type
- When you load a file from a plane that is not exactly the same but similar, X-Camera will optionally attempt to fix all the cockpit cameras

These enhancements should encourage more users to share their camera definitions. They will also make it a lot easier for new users to take advantage of X-Camera without the need to go through the tedious task of setting up all the camera definitions from scratch.

The community aircraft file server has been updated with the most recent submitted aircraft definition files. These include new files as well as enhancement to existing files. The first time you “Check for Updates” X-Camera will download these new files and remove any obsolete files in your local Community Aircraft file Cache. The cache update will not have an effect on any of your current camera definitions that are stored in the aircraft directories. That said, we always recommend making a backup copy of your X-Camera directory in case you need to revert to the previous version of X-Camera.

More detail about the submitting aircraft files and browsing existing community files can be found in the corresponding section of this manual.

Please note that the “Generate Airport Cameras” button has been moved to the upper right corner of the control panel when you are working with an airport camera file.

## Mini-Control Panel

The Mini-Control Panel has been enhanced in a number of different ways. An option has been added to the settings dialog to support a translucent Mini-Control Panel. When this setting is enabled the Mini-Control Panel will have a translucent look similar to the main control panel.

The Mini-Control Panel also has two new rows added. The first row is a context sensitive set of command buttons that changes based upon the type of camera that is currently selected. Depending on the current camera you can use these command buttons to:

- Select airport cameras
- Select the nearest airport camera
- Auto select the nearest airport camera
- Open the main control panel
- Select aircraft cameras when airport cameras are active
- Home a Cineplex camera
- Select free, next, previous, and nearest targets for a target following camera

An additional row will also be added if the camera definition file has any cameras with View\_IDs assigned. These are essentially a set of favorite cameras and they can be selected from the mini-control panel regardless of the type of camera, category, or current camera that is selected.

The mini-control panel also has a pin function that allows you to pin the panel open until it is unchecked.

### 2.1.1

This is primarily a patch release to fix some bugs that are outlined in the change log section above. We also added some new community aircraft files that were submitted since X-Camera 2.1. We have also made a partial correction to an X-Plane 11 Beta 1 problem with external cameras when the simulator has been paused.

## 2.1

## External Cameras

Ever since we introduced external cameras there has been a minor problem where the external camera was not being properly rotated in relation to the aircraft's roll and pitch. You could really see this problem if you had an external chase view and tried to do a barrel roll, the camera placement did not follow the plane properly. This has been fixed now.

## Responding to ATC with Commands

Due to some recent changes in X-Plane a conflict arose around the X-Plane `general_up` and `general_down` commands with regard to using these to respond to ATC. X-Camera had these commands mapped to camera move up and down and was intercepting the commands when the ATC window was open. We added a new option in the X-Camera settings dialog that allows you to lock out keyboard control for camera movement when the X-Camera control panel is not open. When this option is set you will not be able to move the camera with the keyboard if the control panel is not open but the commands will go to the ATC window restoring the ATC response functionality.

## Scenic Flyer Integration

We have also integrated X-Camera to the Scenic Flyer plugin:

<http://www.digital-avionics.com/scenic/home.html>

If this optional plugin is installed you can specify by camera when you want the Scenic Flyer panel to be shown and what flavor of panel you would like. Note: Scenic Flyer is not available for Linux at this time.

We have also collected all the community aircraft files submitted to date and added them to the X-Camera distribution zip file. You will be able to access them when you Browse Community Aircraft from the control panel.

## Zooming on External Cameras

Prior to 2.1 you had to use a mapped command to zoom in the external views. Zooming with the scroll wheel is now supported and in addition a mouse zoom command has been added to allow for very rapid zooming of external views using mouse movement.

## Targets and Target Following Cameras

2.1 adds a significant new feature to X-Camera, Targets. Targets are locations defined by latitude, longitude, and elevation in meters that can act as targets that target tracking cameras can follow. See the Targets section of this manual for more detail.

## Restoring Camera

There is a new command that will allow you to not only restore the cameras from the previously saved camera file but it will also select the first category and camera. This is similar to what you get when you first load a plane that has a camera file. The command to map is:

`"SRS/X-Camera/Restore_Cameras_And_Home"`

## X-Plane 9 Chase View

An X-Plane 9 chase view has been added. Many users claim they prefer the X-Plane chase view over the built-in X-Plane 10 chase view. This camera option comes close to replicating the behavior of the X-Plane 9 chase view.

## Airport Cameras

There is a new option for airport cameras that will continuously evaluate which airport camera is closest to your moving plane and will automatically select that camera. The continuous evaluation is only done when you have an airport camera file loaded. It does not take place when while in an aircraft camera file. Two new commands have been added to allow you to enable this capability:

`"SRS/X-Camera/Auto_Select_Nearest_Airport_Camera"`  
`"SRS/X-Camera/Toggle_Auto_Nearest_Airport_Camera"`

There was a design flaw in the X-Camera airport cameras that made an assumption that the X-Plane coordinate system would remain consistent as you switched between airports. X-Camera was saving the local coordinates for an airport camera when it should have been saving Lat, Long, and Elevation.

The problem manifests itself by having cameras improperly placed at airports when a previously saved airport camera was selected. The camera would often be under ground and nowhere near the airport. If you are still running X-Plane 10.36 or lower we recommend that you load and resave all your airport camera files so that each camera's Lat, Long, and elevation will be properly saved making the file compatible with X-Plane 10.4. Should you forget to do this it may be necessary to regenerate your airport camera files when you upgrade to X-Plane 10.4.

## Roll Support

Camera roll support, including transition support, has been added. This allows you to specify a camera roll offset for a camera.

## 2.0

A System Check menu item has been added that will verify your X-Plane's configuration is compatible with X-Camera. X-Camera must be enabled on an aircraft for the System Check to work.

We added an X-Camera command to toggle HeadShake on or off for the current camera.

We have added a mini control panel that can be activated by a command mapping or optionally if you place your mouse in the bottom 5 pixels of the X-Plane window. The mini control panel will allow you to rapidly select categories and the first cameras in that category that will fit on the min panel.

We have also added an ability to browse community aircraft camera files which are located in the X-Camera/CommunityAircraftCameras directory. This allows you to import existing camera definitions for an aircraft or one from a similar aircraft so you can more rapidly setup a new plane.

We also added an Author and version field for the camera files so that if you choose to share your camera definitions with the X-Camera community people can see who created it and what version the file is at.

Categories have been increased from ten to twenty.

A toggle walk mode command has been added that will allow you to map a joy stick to that command.

A mouse move feature has been added that dramatically improves the ability to move and place cameras. This feature works very similar to mouse look and can be used for X-Y, X-Z, and heading-pitch camera adjustments using the mouse and thee mapped commands. We also added an option to adjust the mouse smoothing factor for mouse look and move. This is a new option on the settings panel.

A forth movement range has been added, Very Large. This larger range is useful for placing free cameras of very large distances. It is highly likely that you will want to adjust your range settings when they are used with the mouse moving feature. The mouse can place the camera much faster than the keyboard so you may find it necessary to reduce the medium and large movement ranges in the settings panel.

Parameter driven Orbit and Fly-by animation generators have been added that will allow you to more easily create orbit and fly-by animations.

Transitions can be specified in seconds. When this option is used for the three transition types, X-Camera will calculate the required number of transition and the time of animation based on the simulators current frame rate.

You can post your aircraft camera files and download other user's aircraft camera files by going to our community files page:

[Stick and Rudder Studios – All Community Files](#)

See the Sharing Files section of this manual for greater details.

We added support for a major new feature, Airport cameras. Airport cameras are a set of up to 1,000 cameras per file that can be associated with a specific airport or a set of airports in very close proximity to each other. Airport cameras are typically free cameras that are not attached to a plane, although there is no restriction on their definition.

You can design runway, taxiway, tower, gate, and observation cameras on nearby mountains or structures. Airport cameras are automatically selected based on how close your plane is to the airport



the camera file is associated with. You can toggle between your aircraft cameras, last selected airport camera, or nearest airport camera in relation to the plane's current position.

X-Camera can populate an airport camera file automatically from the corresponding airport's scenery. Cameras will be placed at runways, starting locations, airport viewpoints, and taxiway signs.

**Note:** This feature is only available X-Plane 10 or above as it relies on some enhancements to the X-Plane scenery system that was not available in X-Plane 9. Generated files may still work on X-Plane 9 assuming that the scenery files used are also compatible with X-Plane 9.

X-Camera supports two types of Airport Camera files, My Airport Camera Files, and Community Airport Camera Files. The idea behind the Community Airport Camera Files is that they can be shared with the X-Camera user community on the Stick and Rudder Studio's website or on other simulator forums such as AVSIM or X-Plane.org. X-Camera will always select the matching "My Airport Camera File" over a matching community file.

You can post your airport camera files and download other user's airport camera files by going to our community files page:

[Stick and Rudder Studios – All Community Files](#)

[See the Tutorial Link 13](#)

## AI Perspective

By default the orientation of any external "non-free" camera is oriented relative to the user's aircraft. X-Camera has the ability to change that orientation to any of the configured X-Plane AI aircraft. As an example, if you have a tail camera setup on your plane and you have AI planes configured in X-Plane you can toggle the orientation to an AI perspective and your camera will now give you a tail view of the currently selected AI plane.

You can toggle AI perspective on or off from the Mini Control panel. You can also select the next or previous AI plane from the Mini Control panel.

**Note:** You must have some AI planes configured and you must have an external camera selected. AI orientation does not work with internal cockpit cameras.

There are also five commands you can map to keys or joystick buttons that will toggle AI orientations and allow you to select AI aircraft.

6. "SRS/X-Camera/Toggle\_AI\_Perspective"
7. "SRS/X-Camera/Select\_Next\_AI\_Plane"
8. "SRS/X-Camera/Select\_Previous\_AI\_Plane"
9. "SRS/X-Camera/AI\_Scale\_Up"
10. "SRS/X-Camera/AI\_Scale\_Down"

When you have a free camera, such as an airport camera, and you have pitch and heading tracking on the camera will track the currently selected AI plane when AI perspective is enabled.

There are some limitations to AI perspective:

- X-Camera is not currently aware of the size difference between your plane and the AI aircraft. A tail view on a Cessana 172 that is only ten meters away from plane's center of gravity is going to be to be in the middle of a 747's fuselage when you select AI perspective.

There is a potential for X-Camera to be smarter about this in the future so that it can either up-scale and down-scale the cameras based on the difference between the users aircraft size and the selected AI plane. In the mean time scale up and scale down buttons will appear in the mini control panel when AI Perspective is enabled.

These buttons will add a scaling modifier to the camera coordinates to move it in or out allowing you to adjust for the difference in plane size. The scaling is temporary and does not affect the camera definitions in your camera file.

- AI Aircraft can roam a fair distance from your user's aircraft. Your scenery may not render to the same fidelity when you have an AI perspective selected.
- Do not expect to hear the sounds from an AI plane. As a matter of fact, some user aircraft sound systems are not that sophisticated and they may not be aware of the fact that your camera is many miles away from the user's plane when AI perspective is selected. It is not uncommon to hear the sounds of your Baron 58 even when you have an AI perspective on a heavy metal 747.

<https://www.youtube.com/watch?v=SAP-ySvCtIc&t=17m46s>

[Tutorial Link 14](#)

Airport Cameras section of this manual for greater detail.

A major new transition type, Bezier Curve Transitions, has been added to X-Camera. This transition type will join between 3 – 32 cameras using a 3D Bezier curve algorithm. The result is an ultra-smooth animation with no discernable stitch at the camera join points. This Wikipedia entry explains the math behind this transition:

[http://en.wikipedia.org/wiki/Bezier\\_curve](http://en.wikipedia.org/wiki/Bezier_curve)

We have also added an option in the control panel to allow auto advance while the control panel is open. Previous versions of X-Camera would not allow the full animation to be seen while the control panel was open. This limitation was imposed so that you could still select individual cameras for editing without the auto advance feature getting in the way and selecting cameras in a sequence automatically.

With this new control panel option you can temporarily enable the auto advances so you can preview the entire animation without having to close the control panel. It can easily be disabled to allow selection and editing of individual cameras.

X-Camera now has the ability to insert cameras or categories with the control panel. Prior to this release added cameras and categories would always be added at the end of the list.

Cameras will now remember the last movement range setting that was used to position them. This is most useful for external cameras that may require a large range setting to move them affectively when they are selected.

We added support for external cameras. External cameras are needed for two basic reasons. The first is that some aircraft will not render properly when viewing them from the outside while still in 3D cockpit mode. We have also had some reports that external sounds do not always work properly when the camera is placed outside the cockpit using the 3D cockpit view. The second reason we need them is to ultimately support world / airport cameras. These are cameras that are not attached to the plane, basically a free camera.

Three external cameras have been added as part of this beta release.

- External Camera
  - This is a basic external camera that is still attached to the plane but it uses the X-Plane free camera view so planes like the Flight Factor 777 should render properly.
- Cineflex Camera
  - This is similar to a basic external camera but the camera's heading and pitch do not track the plane's heading and pitch. You can point the Cineflex camera in a specific heading and it will retain that heading regardless of the plane's movement. We are ultimately attempting to simulate the Cineflex cameras that are often attached to the nose of helicopters.
- Free Camera
  - This is a camera that is not attached to the plane and it stays stationary to the world location that you created it at. The camera can be aimed and moved independently of the plane. It can also be setup to track the plane's location by using the track heading and pitch options available to other cameras. Our hope is to introduce the concept of an airport category where you can setup a series of external free cameras around the airport. I can envision a feature where these airport cameras get loaded automatically when you place your plane at an airport or you get close to an airport that has cameras defined for it.

There are some limitations when using external cameras. In X-Plane 9 virtually any other view will not be available if X-Camera is enabled and the current camera is an external camera of some flavor. X-Camera latterly needs to hijack the entire view system of X-Plane 9 in order to make external cameras work.

X-Plane 10 is much less affected by this. X-Camera uses the "Free Camera" view to implement external cameras. While X-Camera is displaying an external camera the traditional functionality of the Free Camera view will not be available. However, all the other views, like chase, etc. should still work.

## 1.1

X-Camera's keyboard mapping went through a considerable change with this version. Many of the original keyboard commands to move the camera around have been removed and replaced with the

equivalent X-Plane commands. The reason for this change was to allow for a better user experience when alternating between X-Plane's default view system and X-Camera's view system.

An example of this is the HAT switch. You can leave your HAT switch mapped to X-Plane's panning commands and X-Camera will respond to those same panning commands. The same is true for camera movement with the page-up/down keys and arrow keys.

The original <CTRL> arrow/Page-Up/Page-Down and <CTRL><SHIFT> arrow/Page-Up/Page-Down commands no longer control the camera's movement. Refer to Table 2 for the new list of movement commands.

We have also added a new settings dialog that will allow you to adjust the movement increments over three ranges, Small, Medium, and Large. Within each of these ranges is the concept of a slow, normal, and fast movement setting. The normal and fast settings map to X-Plane 9's concept of normal and fast camera / panning movements. X-Plane 10 supports Slow, Normal, and Fast commands so X-Camera has support for those as well. As an example <CTRL> left arrow, left arrow, and <SHIFT> left arrow will move the camera left by the slow, normal, and fast setting within the current range of small, medium, and large on X-Plane 10. Medium is the default range when X-Camera loads but you can adjust it up or down using the <CTRL> + and - keys.

This release added considerable new features for tracking cameras. A tracking camera has the ability to track the planes center of gravity by modifying the camera's pitch and/or roll to maintain the focal point on the planes center of gravity (CG).

Support has also been added for a special tracking camera called a level camera. A level camera will adjust the camera's pitch and roll so that it remains level with the horizon regardless of the plane's pitch and roll.

Smoothing of camera joins has been added as an option when you use the auto advance feature with transitions. This will smooth out the camera changes allowing you to create chained transitions that appear as one fluid transition.

We have also enhanced the smooth transition feature so that you can specify the number of transition frames. Smooth transitions will be accomplished over 15 frames if the transition frame count is not specified. We also removed the frame delay from the smooth transition code. Previous releases attempted to throttle the smooth transition to roughly 30 frames per second. If you have a very fast CPU you may notice that your smooth transitions are too fast. Simply add a transition frame count to slow them down.

We also added support the X-Plane view axis. If you assign a joystick to the view axis X-Camera will use the input to rotate and pitch the camera according the axis input. Also added a feature to enable and disable view axis input by camera. This is particularly useful when you have a non-spring loaded axis assigned to a view axis and you do not want the input when you switch cameras.

This release added support for specifying a horizontal field of view and an initial zoom factor for each camera. If not specified the FOV will default to the current FOV specified in the X-Plane rendering options. The zoom factor defaults to 1.0.